

Open Source Face Image Quality (OFIQ)

Generated by Doxygen 1.10.0

1 Open Source Face Image Quality (OFIQ) Library	1
1.1 Introduction	1
1.2 License	1
1.2.1 OFIQ License	1
1.2.2 License of dependencies	1
1.3 Compilation	4
1.3.1 Linux	4
1.3.2 Windows	5
1.3.3 Download model files	5
1.3.4 Download conformance test images	5
1.4 Running conformance tests	5
1.5 Running the sample executable	6
1.5.1 Quality assessment for a single facial image	6
1.5.2 Quality assessment for multiple images	6
1.5.3 Arguments	6
1.6 Configuration	7
1.6.1 Configuration of the face detector	8
1.6.2 Configuration of the landmark extractor	8
1.6.3 Other required configurations	9
1.6.4 Requesting measures	9
1.6.5 Default configuration	10
1.6.6 Configuration of the quality mapping	13
1.7 C++ API	14
1.8 Implementation and pre-processing workflow	15
1.9 Release notes	16
1.9.1 Changelog	17
1.9.1.1 Version 1.0.0-RC (2024-03-15)	17
2 Namespace Index	19
2.1 Namespace List	19
3 Hierarchical Index	21
3.1 Class Hierarchy	21
4 Class Index	23
4.1 Class List	23
5 File Index	27
5.1 File List	27
6 Namespace Documentation	31
6.1 cv Namespace Reference	31
6.1.1 Detailed Description	31
6.2 OFIQ Namespace Reference	31

6.2.1 Detailed Description	32
6.2.2 Typedef Documentation	32
6.2.2.1 Landmarks	32
6.2.2.2 QualityAssessments	33
6.2.3 Enumeration Type Documentation	33
6.2.3.1 FaceDetectorType	33
6.2.3.2 LandmarkType	33
6.2.3.3 QualityMeasure	33
6.2.3.4 QualityMeasureReturnCode	34
6.2.3.5 ReturnCode	34
6.2.4 Function Documentation	35
6.2.4.1 operator<<()	35
6.3 OFIQ_LIB Namespace Reference	35
6.3.1 Detailed Description	37
6.3.2 Typedef Documentation	37
6.3.2.1 EulerAngle	37
6.3.2.2 ExposureRange	37
6.3.3 Function Documentation	37
6.3.3.1 alignImage()	37
6.3.3.2 CalculateExposure()	38
6.3.3.3 calculateEyeCenter()	38
6.3.3.4 CalculateReferencePoints()	39
6.3.3.5 CalculateRegionOfInterest()	39
6.3.3.6 ColorConvert()	39
6.3.3.7 ComputeBrightnessAspect()	40
6.3.3.8 ConvertBGRTToCIELAB()	40
6.3.3.9 copyToCvImage()	41
6.3.3.10 Cubic()	41
6.3.3.11 findLargestBoundingBox()	41
6.3.3.12 GetLuminanceImageFromBGR()	42
6.3.3.13 GetNormalizedHistogram()	42
6.3.3.14 MakeGreyImage()	42
6.3.3.15 makeSquareBoundingBox()	43
6.3.3.16 makeSquareBoundingBoxWithPadding()	43
6.3.3.17 readImage()	43
6.3.3.18 rotationMatrixToEulerAngles()	45
6.3.3.19 tmetric()	45
6.4 OFIQ_LIB::modules Namespace Reference	45
6.5 OFIQ_LIB::modules::detectors Namespace Reference	46
6.5.1 Detailed Description	46
6.6 OFIQ_LIB::modules::landmarks Namespace Reference	46
6.6.1 Detailed Description	47

6.6.2 Typedef Documentation	47
6.6.2.1 FaceMap	47
6.6.2.2 FacePairMap	47
6.6.2.3 LandmarkId	48
6.6.2.4 LandmarkIdPair	48
6.6.2.5 LandmarkIdPairs	48
6.6.2.6 LandmarkIds	48
6.6.3 Enumeration Type Documentation	48
6.6.3.1 FaceParts	48
6.7 OFIQ_LIB::modules::landmarks::adnet Namespace Reference	49
6.7.1 Detailed Description	49
6.7.2 Variable Documentation	49
6.7.2.1 chin	49
6.7.2.2 contour	50
6.7.2.3 FaceMap	50
6.7.2.4 FacePairMap	50
6.7.2.5 forehead	50
6.7.2.6 leftEye	50
6.7.2.7 leftEyeCorners	51
6.7.2.8 mouthInner	51
6.7.2.9 mouthOuter	51
6.7.2.10 nosetip	51
6.7.2.11 pairsInnerLip	51
6.7.2.12 pairsLeftEye	51
6.7.2.13 pairsMouthCenter	52
6.7.2.14 pairsRightEye	52
6.7.2.15 rightEye	52
6.7.2.16 rightEyeCorners	52
6.8 OFIQ_LIB::modules::measures Namespace Reference	52
6.8.1 Detailed Description	54
6.8.2 Function Documentation	54
6.8.2.1 log()	54
6.8.3 Variable Documentation	54
6.8.3.1 execLogActive	54
6.9 OFIQ_LIB::modules::poseEstimators Namespace Reference	54
6.9.1 Detailed Description	55
6.10 OFIQ_LIB::modules::segmentations Namespace Reference	55
6.10.1 Detailed Description	55
6.10.2 Enumeration Type Documentation	55
6.10.2.1 SegmentClassLabels	55
7 Class Documentation	57

7.1 OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor Class Reference	57
7.1.1 Detailed Description	58
7.1.2 Constructor & Destructor Documentation	58
7.1.2.1 ADNetFaceLandmarkExtractor()	58
7.1.2.2 ~ADNetFaceLandmarkExtractor()	58
7.1.3 Member Function Documentation	58
7.1.3.1 updateLandmarks()	58
7.1.4 Member Data Documentation	59
7.1.4.1 landmarkExtractor	59
7.2 OFIQ_LIB::modules::measures::BackgroundUniformity Class Reference	59
7.2.1 Detailed Description	61
7.2.2 Constructor & Destructor Documentation	61
7.2.2.1 BackgroundUniformity()	61
7.2.3 Member Function Documentation	61
7.2.3.1 Execute()	61
7.2.4 Member Data Documentation	61
7.2.4.1 m_crop_bottom	61
7.2.4.2 m_crop_left	62
7.2.4.3 m_crop_right	62
7.2.4.4 m_crop_top	62
7.2.4.5 m_erosion_kernel_size	62
7.2.4.6 m_target_height	62
7.2.4.7 m_target_width	62
7.3 OFIQ::BoundingBox Struct Reference	63
7.3.1 Detailed Description	63
7.3.2 Constructor & Destructor Documentation	63
7.3.2.1 BoundingBox() [1/2]	63
7.3.2.2 BoundingBox() [2/2]	63
7.3.3 Member Data Documentation	64
7.3.3.1 faceDetector	64
7.3.3.2 height	64
7.3.3.3 width	64
7.3.3.4 xleft	64
7.3.3.5 ytop	64
7.4 OFIQ_LIB::modules::measures::CompressionArtifacts Class Reference	65
7.4.1 Detailed Description	66
7.4.2 Constructor & Destructor Documentation	66
7.4.2.1 CompressionArtifacts()	66
7.4.3 Member Function Documentation	67
7.4.3.1 Execute()	67
7.4.4 Member Data Documentation	67
7.4.4.1 m_crop	67

7.4.4.2 m_dim	68
7.4.4.3 m_onnxRuntimeEnv	68
7.5 OFIQ_LIB::Configuration Class Reference	68
7.5.1 Detailed Description	69
7.5.2 Constructor & Destructor Documentation	69
7.5.2.1 Configuration()	69
7.5.3 Member Function Documentation	69
7.5.3.1 GetBool() [1/2]	69
7.5.3.2 GetBool() [2/2]	70
7.5.3.3 getDataDir()	70
7.5.3.4 GetNumber() [1/2]	70
7.5.3.5 GetNumber() [2/2]	71
7.5.3.6 GetString() [1/2]	71
7.5.3.7 GetString() [2/2]	72
7.5.3.8 GetStringList()	72
7.5.3.9 SetDataDir()	72
7.5.4 Member Data Documentation	73
7.5.4.1 m_dataDir	73
7.5.4.2 parameters	73
7.6 OFIQ_LIB::modules::measures::CropOfTheFacelImage Class Reference	73
7.6.1 Detailed Description	74
7.6.2 Constructor & Destructor Documentation	74
7.6.2.1 CropOfTheFacelImage()	74
7.6.3 Member Function Documentation	75
7.6.3.1 Execute()	75
7.7 OFIQ_LIB::modules::measures::DynamicRange Class Reference	75
7.7.1 Detailed Description	76
7.7.2 Constructor & Destructor Documentation	76
7.7.2.1 DynamicRange()	76
7.7.3 Member Function Documentation	77
7.7.3.1 Execute()	77
7.8 OFIQ_LIB::modules::measures::Executor Class Reference	77
7.8.1 Detailed Description	78
7.8.2 Constructor & Destructor Documentation	78
7.8.2.1 Executor()	78
7.8.3 Member Function Documentation	78
7.8.3.1 ExecuteAll()	78
7.8.3.2 GetMeasures()	78
7.8.4 Member Data Documentation	78
7.8.4.1 measures	78
7.9 OFIQ_LIB::modules::measures::ExpressionNeutrality Class Reference	79
7.9.1 Detailed Description	80

7.9.2 Constructor & Destructor Documentation	80
7.9.2.1 ExpressionNeutrality()	80
7.9.3 Member Function Documentation	81
7.9.3.1 Execute()	81
7.9.4 Member Data Documentation	81
7.9.4.1 classifier	81
7.9.4.2 m_onnxRuntimeEnvCNN1	81
7.9.4.3 m_onnxRuntimeEnvCNN2	81
7.10 OFIQ_LIB::modules::measures::EyesOpen Class Reference	82
7.10.1 Detailed Description	83
7.10.2 Constructor & Destructor Documentation	83
7.10.2.1 EyesOpen()	83
7.10.3 Member Function Documentation	83
7.10.3.1 Execute()	83
7.11 OFIQ_LIB::modules::measures::EyesVisible Class Reference	84
7.11.1 Detailed Description	85
7.11.2 Constructor & Destructor Documentation	85
7.11.2.1 EyesVisible()	85
7.11.3 Member Function Documentation	86
7.11.3.1 Execute()	86
7.12 OFIQ_LIB::FaceDetectorInterface Class Reference	86
7.12.1 Detailed Description	87
7.12.2 Constructor & Destructor Documentation	87
7.12.2.1 ~FaceDetectorInterface()	87
7.12.3 Member Function Documentation	87
7.12.3.1 detectFaces()	87
7.12.3.2 UpdateFaces()	87
7.13 OFIQ::FacelImageQualityAssessment Struct Reference	88
7.13.1 Detailed Description	88
7.13.2 Constructor & Destructor Documentation	88
7.13.2.1 FacelImageQualityAssessment() [1/2]	88
7.13.2.2 FacelImageQualityAssessment() [2/2]	88
7.13.3 Member Data Documentation	89
7.13.3.1 boundingBox	89
7.13.3.2 qAssessments	89
7.14 OFIQ_LIB::FaceLandmarkExtractorInterface Class Reference	89
7.14.1 Detailed Description	89
7.14.2 Constructor & Destructor Documentation	90
7.14.2.1 ~FaceLandmarkExtractorInterface()	90
7.14.3 Member Function Documentation	90
7.14.3.1 extractLandmarks()	90
7.14.3.2 updateLandmarks()	90

7.15 OFIQ::FaceLandmarks Struct Reference	91
7.15.1 Detailed Description	91
7.15.2 Constructor & Destructor Documentation	91
7.15.2.1 FaceLandmarks()	91
7.15.3 Member Data Documentation	91
7.15.3.1 landmarks	91
7.15.3.2 type	91
7.16 OFIQ_LIB::modules::landmarks::FaceMeasures Class Reference	92
7.16.1 Detailed Description	92
7.16.2 Constructor & Destructor Documentation	92
7.16.2.1 FaceMeasures()	92
7.16.3 Member Function Documentation	92
7.16.3.1 GetDistance() [1/2]	92
7.16.3.2 GetDistance() [2/2]	93
7.16.3.3 GetFaceMask()	93
7.16.3.4 GetMaxPairDistance()	94
7.16.3.5 GetMiddle() [1/3]	94
7.16.3.6 GetMiddle() [2/3]	94
7.16.3.7 GetMiddle() [3/3]	95
7.16.3.8 InterEyeDistance()	95
7.17 OFIQ_LIB::modules::measures::FaceOcclusionPrevention Class Reference	96
7.17.1 Detailed Description	97
7.17.2 Constructor & Destructor Documentation	97
7.17.2.1 FaceOcclusionPrevention()	97
7.17.3 Member Function Documentation	97
7.17.3.1 Execute()	97
7.18 OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation Class Reference	98
7.18.1 Detailed Description	99
7.18.2 Constructor & Destructor Documentation	99
7.18.2.1 FaceOcclusionSegmentation()	99
7.18.2.2 ~FaceOcclusionSegmentation()	100
7.18.3 Member Function Documentation	100
7.18.3.1 GetFaceOcclusionSegmentation()	100
7.18.3.2 UpdateMask()	100
7.18.4 Member Data Documentation	101
7.18.4.1 cropBottom	101
7.18.4.2 cropLeft	101
7.18.4.3 cropRight	101
7.18.4.4 cropTop	101
7.18.4.5 m_onnxRuntimeEnv	101
7.18.4.6 modelConfigItem	102
7.18.4.7 scaledHeight	102

7.18.4.8 scaledWidth	102
7.18.4.9 segmentationImage	102
7.19 OFIQ_LIB::modules::segmentations::FaceParsing Class Reference	102
7.19.1 Detailed Description	104
7.19.2 Constructor & Destructor Documentation	104
7.19.2.1 FaceParsing()	104
7.19.2.2 ~FaceParsing()	105
7.19.3 Member Function Documentation	105
7.19.3.1 CalculateClassIds()	105
7.19.3.2 CreateBlob()	105
7.19.3.3 SetImage()	106
7.19.3.4 UpdateMask()	106
7.19.4 Member Data Documentation	106
7.19.4.1 cropBottom	106
7.19.4.2 cropLeft	106
7.19.4.3 cropRight	107
7.19.4.4 cropTop	107
7.19.4.5 imageSize	107
7.19.4.6 m_onnxRuntimeEnv	107
7.19.4.7 modelConfigItem	107
7.19.4.8 segmentationImage	107
7.20 OFIQ_LIB::modules::measures::HeadPose Class Reference	108
7.20.1 Detailed Description	109
7.20.2 Constructor & Destructor Documentation	109
7.20.2.1 HeadPose()	109
7.20.3 Member Function Documentation	109
7.20.3.1 Execute()	109
7.21 OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2 Class Reference	110
7.21.1 Detailed Description	111
7.21.2 Constructor & Destructor Documentation	111
7.21.2.1 HeadPose3DDFAV2()	111
7.21.2.2 ~HeadPose3DDFAV2()	112
7.21.3 Member Function Documentation	112
7.21.3.1 CropImage()	112
7.21.3.2 updatePose()	112
7.21.4 Member Data Documentation	112
7.21.4.1 inputShape	112
7.21.4.2 m_expected_image_height	113
7.21.4.3 m_expected_image_number_of_channels	113
7.21.4.4 m_expected_image_width	113
7.21.4.5 m_number_of_input_elements	113
7.21.4.6 m_ort_session	113

7.21.4.7 m_ortenv	113
7.21.4.8 paramPoseEstimatorModel	113
7.22 OFIQ_LIB::modules::measures::HeadSize Class Reference	114
7.22.1 Detailed Description	115
7.22.2 Constructor & Destructor Documentation	115
7.22.2.1 HeadSize()	115
7.22.3 Member Function Documentation	115
7.22.3.1 Execute()	115
7.23 OFIQ_LIB::modules::measures::IlluminationUniformity Class Reference	116
7.23.1 Detailed Description	117
7.23.2 Constructor & Destructor Documentation	117
7.23.2.1 IlluminationUniformity()	117
7.23.3 Member Function Documentation	118
7.23.3.1 Execute()	118
7.24 OFIQ::Image Struct Reference	118
7.24.1 Detailed Description	118
7.24.2 Constructor & Destructor Documentation	119
7.24.2.1 Image() [1/2]	119
7.24.2.2 Image() [2/2]	119
7.24.3 Member Function Documentation	119
7.24.3.1 size()	119
7.24.4 Member Data Documentation	119
7.24.4.1 data	119
7.24.4.2 depth	119
7.24.4.3 height	120
7.24.4.4 width	120
7.25 OFIQ_LIB::modules::measures::InterEyeDistance Class Reference	120
7.25.1 Detailed Description	121
7.25.2 Constructor & Destructor Documentation	121
7.25.2.1 InterEyeDistance()	121
7.25.3 Member Function Documentation	122
7.25.3.1 Execute()	122
7.26 OFIQ::Interface Class Reference	122
7.26.1 Detailed Description	123
7.26.2 Constructor & Destructor Documentation	123
7.26.2.1 ~Interface()	123
7.26.3 Member Function Documentation	123
7.26.3.1 getImplementation()	123
7.26.3.2 initialize()	123
7.26.3.3 scalarQuality()	124
7.26.3.4 vectorQuality()	124
7.27 OFIQ_LIB::modules::landmarks::LandmarkPair Struct Reference	125

7.27.1 Detailed Description	125
7.27.2 Constructor & Destructor Documentation	125
7.27.2.1 LandmarkPair()	125
7.27.3 Member Data Documentation	126
7.27.3.1 Lower	126
7.27.3.2 Upper	126
7.28 OFIQ::LandmarkPoint Struct Reference	126
7.28.1 Detailed Description	127
7.28.2 Constructor & Destructor Documentation	127
7.28.2.1 LandmarkPoint() [1/2]	127
7.28.2.2 LandmarkPoint() [2/2]	127
7.28.3 Member Data Documentation	127
7.28.3.1 x	127
7.28.3.2 y	127
7.29 OFIQ_LIB::modules::measures::Luminance Class Reference	128
7.29.1 Detailed Description	129
7.29.2 Constructor & Destructor Documentation	129
7.29.2.1 Luminance()	129
7.29.3 Member Function Documentation	129
7.29.3.1 Execute()	129
7.30 OFIQ_LIB::modules::measures::Measure Class Reference	130
7.30.1 Detailed Description	131
7.30.2 Constructor & Destructor Documentation	132
7.30.2.1 Measure()	132
7.30.2.2 ~Measure()	132
7.30.3 Member Function Documentation	132
7.30.3.1 AddSigmoid() [1/2]	132
7.30.3.2 AddSigmoid() [2/2]	132
7.30.3.3 Execute()	133
7.30.3.4 ExecuteScalarConversion() [1/2]	133
7.30.3.5 ExecuteScalarConversion() [2/2]	134
7.30.3.6 ExpandKey()	134
7.30.3.7 GetMeasureName()	134
7.30.3.8 GetName()	135
7.30.3.9 GetQualityMeasure()	135
7.30.3.10 ScalarConversion()	135
7.30.3.11 SetQualityMeasure()	136
7.30.3.12 Sigmoid()	136
7.30.4 Member Data Documentation	136
7.30.4.1 configuration	136
7.30.4.2 m_measure	137
7.30.4.3 sigmoidMap	137

7.31 OFIQ_LIB::modules::measures::MeasureFactory Class Reference	137
7.31.1 Detailed Description	137
7.31.2 Constructor & Destructor Documentation	137
7.31.2.1 MeasureFactory()	137
7.31.3 Member Function Documentation	137
7.31.3.1 CreateMeasure()	137
7.32 OFIQ_LIB::modules::measures::MouthClosed Class Reference	138
7.32.1 Detailed Description	139
7.32.2 Constructor & Destructor Documentation	139
7.32.2.1 MouthClosed()	139
7.32.3 Member Function Documentation	140
7.32.3.1 Execute()	140
7.33 OFIQ_LIB::modules::measures::MouthOcclusionPrevention Class Reference	140
7.33.1 Detailed Description	141
7.33.2 Constructor & Destructor Documentation	141
7.33.2.1 MouthOcclusionPrevention()	141
7.33.3 Member Function Documentation	142
7.33.3.1 Execute()	142
7.34 OFIQ_LIB::modules::measures::NaturalColour Class Reference	142
7.34.1 Detailed Description	144
7.34.2 Constructor & Destructor Documentation	144
7.34.2.1 NaturalColour()	144
7.34.3 Member Function Documentation	144
7.34.3.1 CalculateScore()	144
7.34.3.2 CreateMaskedImage()	145
7.34.3.3 Execute()	145
7.34.3.4 ReducelImageToRegionOfInterest()	145
7.35 OFIQ_LIB::NeuronalNetworkContainer Struct Reference	146
7.35.1 Detailed Description	146
7.35.2 Constructor & Destructor Documentation	146
7.35.2.1 NeuronalNetworkContainer()	146
7.35.3 Member Data Documentation	147
7.35.3.1 faceDetector	147
7.35.3.2 faceOcclusionExtractor	147
7.35.3.3 landmarkExtractor	147
7.35.3.4 poseEstimator	147
7.35.3.5 segmentationExtractor	147
7.36 OFIQ_LIB::modules::measures::NoHeadCoverings Class Reference	148
7.36.1 Detailed Description	149
7.36.2 Constructor & Destructor Documentation	149
7.36.2.1 NoHeadCoverings()	149
7.36.3 Member Function Documentation	150

7.36.3.1 Execute()	150
7.36.4 Member Data Documentation	150
7.36.4.1 threshold	150
7.37 OFIQ_LIB::OFIQError Class Reference	150
7.37.1 Detailed Description	151
7.37.2 Constructor & Destructor Documentation	151
7.37.2.1 OFIQError()	151
7.37.3 Member Function Documentation	151
7.37.3.1 what()	151
7.37.3.2 whatCode()	152
7.37.4 Member Data Documentation	152
7.37.4.1 extendedMessage	152
7.37.4.2 message	152
7.37.4.3 returnCode	152
7.38 OFIQ_LIB::OFIQImpl Class Reference	152
7.38.1 Detailed Description	154
7.38.2 Constructor & Destructor Documentation	154
7.38.2.1 OFIQImpl()	154
7.38.2.2 ~OFIQImpl()	154
7.38.3 Member Function Documentation	154
7.38.3.1 alignFacelImage()	154
7.38.3.2 CreateExecutor()	154
7.38.3.3 CreateNetworks()	155
7.38.3.4 initialize()	155
7.38.3.5 performPreprocessing()	155
7.38.3.6 scalarQuality()	155
7.38.3.7 vectorQuality()	156
7.38.4 Member Data Documentation	156
7.38.4.1 config	156
7.38.4.2 dummyAssement	156
7.38.4.3 dummyImage	157
7.38.4.4 m_emptySession	157
7.38.4.5 m_executorPtr	157
7.38.4.6 networks	157
7.39 ONNXRuntimeSegmentation Class Reference	157
7.39.1 Detailed Description	158
7.39.2 Constructor & Destructor Documentation	158
7.39.2.1 ONNXRuntimeSegmentation()	158
7.39.2.2 ~ONNXRuntimeSegmentation()	158
7.39.3 Member Function Documentation	158
7.39.3.1 getNumberOfOutputNodes()	158
7.39.3.2 init_session()	158

7.39.3.3 initialize()	159
7.39.3.4 run()	159
7.39.4 Member Data Documentation	159
7.39.4.1 m_inputShape	159
7.39.4.2 m_memory_info	160
7.39.4.3 m_ort_session	160
7.39.4.4 m_ortenv	160
7.40 OFIQ_LIB::modules::measures::OverExposurePrevention Class Reference	160
7.40.1 Detailed Description	161
7.40.2 Constructor & Destructor Documentation	161
7.40.2.1 OverExposurePrevention()	161
7.40.3 Member Function Documentation	162
7.40.3.1 Execute()	162
7.41 OFIQ_LIB::modules::landmarks::PartExtractor Class Reference	162
7.41.1 Detailed Description	162
7.41.2 Member Function Documentation	162
7.41.2.1 getFacePart()	162
7.41.2.2 getPairsForPart()	163
7.42 Point2f Struct Reference	163
7.42.1 Detailed Description	163
7.42.2 Member Data Documentation	164
7.42.2.1 x	164
7.42.2.2 y	164
7.43 OFIQ_LIB::Point2i Struct Reference	164
7.43.1 Detailed Description	164
7.43.2 Member Data Documentation	164
7.43.2.1 x	164
7.43.2.2 y	164
7.44 OFIQ_LIB::PoseEstimatorInterface Class Reference	165
7.44.1 Detailed Description	165
7.44.2 Member Typedef Documentation	165
7.44.2.1 EulerAngle	165
7.44.3 Constructor & Destructor Documentation	166
7.44.3.1 ~PoseEstimatorInterface()	166
7.44.4 Member Function Documentation	166
7.44.4.1 estimatePose()	166
7.44.4.2 updatePose()	166
7.44.5 Member Data Documentation	166
7.44.5.1 lastSessionId	166
7.44.5.2 pose	167
7.45 OFIQ::QualityMeasureResult Struct Reference	167
7.45.1 Detailed Description	167

7.45.2 Constructor & Destructor Documentation	167
7.45.2.1 QualityMeasureResult() [1/2]	167
7.45.2.2 QualityMeasureResult() [2/2]	167
7.45.3 Member Data Documentation	168
7.45.3.1 code	168
7.45.3.2 rawScore	168
7.45.3.3 scalar	168
7.46 OFIQ::ReturnStatus Struct Reference	168
7.46.1 Detailed Description	169
7.46.2 Constructor & Destructor Documentation	169
7.46.2.1 ReturnStatus() [1/2]	169
7.46.2.2 ReturnStatus() [2/2]	169
7.46.3 Member Data Documentation	169
7.46.3.1 code	169
7.46.3.2 info	170
7.47 OFIQ_LIB::SegmentationExtractorInterface Class Reference	170
7.47.1 Detailed Description	171
7.47.2 Constructor & Destructor Documentation	171
7.47.2.1 ~SegmentationExtractorInterface()	171
7.47.3 Member Function Documentation	171
7.47.3.1 GetLastSessionId()	171
7.47.3.2 GetMask()	171
7.47.3.3 UpdateMask()	172
7.47.4 Member Data Documentation	172
7.47.4.1 lastSessionId	172
7.47.4.2 masks	172
7.48 OFIQ_LIB::Session Class Reference	172
7.48.1 Detailed Description	174
7.48.2 Constructor & Destructor Documentation	174
7.48.2.1 Session()	174
7.48.3 Member Function Documentation	175
7.48.3.1 assessment()	175
7.48.3.2 GenerateId()	175
7.48.3.3 getAlignedFace()	175
7.48.3.4 getAlignedFaceLandmarkedRegion()	175
7.48.3.5 getAlignedFaceLandmarks()	176
7.48.3.6 getAlignedFaceTransformationMatrix()	176
7.48.3.7 getDetectedFaces()	176
7.48.3.8 getFaceOcclusionSegmentationImage()	176
7.48.3.9 getFaceParsingImage()	176
7.48.3.10 getLandmarks()	177
7.48.3.11 getPose()	177

7.48.3.12	Id()	177
7.48.3.13	image()	177
7.48.3.14	setAlignedFace()	177
7.48.3.15	setAlignedFaceLandmarkedRegion()	178
7.48.3.16	setAlignedFaceLandmarks()	178
7.48.3.17	setAlignedFaceTransformationMatrix()	178
7.48.3.18	setDetectedFaces()	178
7.48.3.19	setFaceOcclusionSegmentationImage()	179
7.48.3.20	setFaceParsingImage()	179
7.48.3.21	setLandmarks()	179
7.48.3.22	setPose()	179
7.48.4	Member Data Documentation	180
7.48.4.1	_assessment	180
7.48.4.2	_image	180
7.48.4.3	alignedFace	180
7.48.4.4	alignedFacelandmarkedRegion	180
7.48.4.5	alignedFaceLandmarks	180
7.48.4.6	alignedFaceTransformationMatrix	180
7.48.4.7	detectedFaces	181
7.48.4.8	faceOcclusionSegmentationImage	181
7.48.4.9	faceParsingImage	181
7.48.4.10	id	181
7.48.4.11	landmarks	181
7.48.4.12	pose	181
7.49	OFIQ_LIB::modules::measures::Sharpness Class Reference	182
7.49.1	Detailed Description	183
7.49.2	Constructor & Destructor Documentation	183
7.49.2.1	Sharpness()	183
7.49.3	Member Function Documentation	184
7.49.3.1	Execute()	184
7.49.3.2	GetClassifierFocusFeatures()	184
7.49.3.3	GetCroppedImages()	184
7.49.4	Member Data Documentation	185
7.49.4.1	faceRegionAlpha	185
7.49.4.2	modelFile	185
7.49.4.3	numTrees	185
7.49.4.4	rtree	185
7.49.4.5	useAligned	185
7.50	OFIQ_LIB::modules::measures::SigmoidParameters Struct Reference	186
7.50.1	Detailed Description	186
7.50.2	Constructor & Destructor Documentation	187
7.50.2.1	SigmoidParameters()	187

7.50.3 Member Function Documentation	187
7.50.3.1 Reset()	187
7.50.3.2 setInverse()	187
7.50.4 Member Data Documentation	187
7.50.4.1 a	187
7.50.4.2 h	187
7.50.4.3 round	188
7.50.4.4 s	188
7.50.4.5 w	188
7.50.4.6 x0	188
7.51 OFIQ_LIB::modules::measures::SingleFacePresent Class Reference	188
7.51.1 Detailed Description	190
7.51.2 Constructor & Destructor Documentation	190
7.51.2.1 SingleFacePresent()	190
7.51.3 Member Function Documentation	190
7.51.3.1 Execute()	190
7.52 OFIQ_LIB::modules::detectors::SSDFaceDetector Class Reference	190
7.52.1 Detailed Description	191
7.52.2 Constructor & Destructor Documentation	191
7.52.2.1 SSDFaceDetector()	191
7.52.2.2 ~SSDFaceDetector()	192
7.52.3 Member Function Documentation	192
7.52.3.1 UpdateFaces()	192
7.52.4 Member Data Documentation	192
7.52.4.1 confidenceThreshold	192
7.52.4.2 dnnNet	192
7.52.4.3 minimalRelativeFaceSize	193
7.52.4.4 padding	193
7.53 OFIQ_LIB::modules::measures::UnderExposurePrevention Class Reference	193
7.53.1 Detailed Description	194
7.53.2 Constructor & Destructor Documentation	194
7.53.2.1 UnderExposurePrevention()	194
7.53.3 Member Function Documentation	195
7.53.3.1 Execute()	195
7.54 OFIQ_LIB::modules::measures::UnifiedQualityScore Class Reference	195
7.54.1 Detailed Description	196
7.54.2 Constructor & Destructor Documentation	196
7.54.2.1 UnifiedQualityScore()	196
7.54.3 Member Function Documentation	197
7.54.3.1 Execute()	197
7.54.4 Member Data Documentation	197
7.54.4.1 m_onnxRuntimeEnv	197

8 File Documentation	199
8.1 mainpage.h File Reference	199
8.1.1 Detailed Description	199
8.2 mainpage.h	199
8.3 ofiq_lib.h File Reference	200
8.3.1 Detailed Description	200
8.3.2 Macro Definition Documentation	201
8.3.2.1 OFIQ_EXPORT	201
8.4 ofiq_lib.h	201
8.5 ofiq_lib_impl.h File Reference	201
8.5.1 Detailed Description	202
8.6 ofiq_lib_impl.h	202
8.7 ofiq_structs.h File Reference	203
8.7.1 Detailed Description	204
8.8 ofiq_structs.h	205
8.9 AllDetectors.h File Reference	208
8.9.1 Detailed Description	208
8.10 AllDetectors.h	208
8.11 detectors.h File Reference	209
8.11.1 Detailed Description	209
8.12 detectors.h	210
8.13 opencv_ssd_face_detector.h File Reference	210
8.13.1 Detailed Description	210
8.14 opencv_ssd_face_detector.h	211
8.15 adnet_FaceMap.h File Reference	211
8.15.1 Detailed Description	213
8.16 adnet_FaceMap.h	213
8.17 adnet_landmarks.h File Reference	214
8.17.1 Detailed Description	215
8.18 adnet_landmarks.h	215
8.19 AllLandmarks.h File Reference	216
8.19.1 Detailed Description	216
8.20 AllLandmarks.h	216
8.21 FaceMeasures.h File Reference	216
8.21.1 Detailed Description	217
8.22 FaceMeasures.h	218
8.23 FaceParts.h File Reference	218
8.23.1 Detailed Description	219
8.24 FaceParts.h	220
8.25 landmarks.h File Reference	220
8.25.1 Detailed Description	221
8.26 landmarks.h	221

8.27 PartExtractor.h File Reference	221
8.27.1 Detailed Description	222
8.28 PartExtractor.h	223
8.29 AllMeasures.h File Reference	223
8.29.1 Detailed Description	224
8.30 AllMeasures.h	224
8.31 BackgroundUniformity.h File Reference	224
8.31.1 Detailed Description	225
8.32 BackgroundUniformity.h	226
8.33 CompressionArtifacts.h File Reference	226
8.33.1 Detailed Description	227
8.34 CompressionArtifacts.h	227
8.35 CropOfTheFacelImage.h File Reference	227
8.35.1 Detailed Description	228
8.36 CropOfTheFacelImage.h	228
8.37 DynamicRange.h File Reference	229
8.37.1 Detailed Description	229
8.38 DynamicRange.h	230
8.39 Executor.h File Reference	230
8.39.1 Detailed Description	231
8.40 Executor.h	231
8.41 ExpressionNeutrality.h File Reference	231
8.41.1 Detailed Description	232
8.42 ExpressionNeutrality.h	232
8.43 EyesOpen.h File Reference	233
8.43.1 Detailed Description	233
8.44 EyesOpen.h	234
8.45 EyesVisible.h File Reference	234
8.45.1 Detailed Description	234
8.46 EyesVisible.h	235
8.47 FaceOcclusionPrevention.h File Reference	235
8.47.1 Detailed Description	236
8.48 FaceOcclusionPrevention.h	236
8.49 HeadPose.h File Reference	237
8.49.1 Detailed Description	237
8.50 HeadPose.h	238
8.51 HeadSize.h File Reference	238
8.51.1 Detailed Description	238
8.52 HeadSize.h	239
8.53 IlluminationUniformity.h File Reference	239
8.53.1 Detailed Description	240
8.54 IlluminationUniformity.h	240

8.55 InterEyeDistance.h File Reference	241
8.55.1 Detailed Description	241
8.56 InterEyeDistance.h	242
8.57 Luminance.h File Reference	242
8.57.1 Detailed Description	242
8.58 Luminance.h	243
8.59 Measure.h File Reference	243
8.59.1 Detailed Description	244
8.60 Measure.h	244
8.61 MeasureFactory.h File Reference	246
8.61.1 Detailed Description	246
8.62 MeasureFactory.h	247
8.63 MouthClosed.h File Reference	247
8.63.1 Detailed Description	247
8.64 MouthClosed.h	248
8.65 MouthOcclusionPrevention.h File Reference	248
8.65.1 Detailed Description	249
8.66 MouthOcclusionPrevention.h	249
8.67 NaturalColour.h File Reference	250
8.67.1 Detailed Description	250
8.68 NaturalColour.h	251
8.69 NoHeadCoverings.h File Reference	251
8.69.1 Detailed Description	252
8.70 NoHeadCoverings.h	252
8.71 OverExposurePrevention.h File Reference	252
8.71.1 Detailed Description	253
8.72 OverExposurePrevention.h	253
8.73 Sharpness.h File Reference	254
8.73.1 Detailed Description	254
8.74 Sharpness.h	255
8.75 SingleFacePresent.h File Reference	255
8.75.1 Detailed Description	256
8.76 SingleFacePresent.h	256
8.77 UnderExposurePrevention.h File Reference	256
8.77.1 Detailed Description	257
8.78 UnderExposurePrevention.h	257
8.79 UnifiedQualityScore.h File Reference	258
8.79.1 Detailed Description	258
8.80 UnifiedQualityScore.h	259
8.81 AllPoseEstimators.h File Reference	259
8.81.1 Detailed Description	259
8.82 AllPoseEstimators.h	260

8.83 HeadPose3DDFAV2.h File Reference	260
8.83.1 Detailed Description	260
8.84 HeadPose3DDFAV2.h	261
8.85 poseEstimators.h File Reference	261
8.85.1 Detailed Description	262
8.86 poseEstimators.h	262
8.87 FaceOcclusionSegmentation.h File Reference	263
8.87.1 Detailed Description	263
8.88 FaceOcclusionSegmentation.h	264
8.89 FaceParsing.h File Reference	264
8.89.1 Detailed Description	265
8.90 FaceParsing.h	265
8.91 ONNXRTSegmentation.h File Reference	266
8.91.1 Detailed Description	266
8.92 ONNXRTSegmentation.h	267
8.93 segmentations.h File Reference	267
8.93.1 Detailed Description	268
8.94 segmentations.h	269
8.95 Configuration.h File Reference	269
8.95.1 Detailed Description	270
8.96 Configuration.h	270
8.97 image_io.h File Reference	271
8.97.1 Detailed Description	271
8.98 image_io.h	272
8.99 image_utils.h File Reference	272
8.99.1 Detailed Description	273
8.100 image_utils.h	273
8.101 NeuronalNetworkContainer.h File Reference	274
8.102 NeuronalNetworkContainer.h	274
8.103 OFIQError.h File Reference	275
8.103.1 Detailed Description	275
8.104 OFIQError.h	276
8.105 Session.h File Reference	276
8.105.1 Detailed Description	277
8.106 Session.h	277
8.107 utils.h File Reference	278
8.107.1 Detailed Description	280
8.108 utils.h	280

Chapter 1

Open Source Face Image Quality (OFIQ) Library

1.1 Introduction

OFIQ (Open Source Face Image Quality) is a software library for computing quality aspects of a facial image. OFIQ is written in the C/C++ programming language. OFIQ is the reference implementation for the ISO/IEC 29794-5 international standard; see <https://bsi.bund.de/dok/OFIQ-e>.

1.2 License

This is the source code of OFIQ. OFIQ is a software for assessing the quality of facial image properties and potential defects. OFIQ is licensed under the MIT licenses (see text below). It includes dependencies that may be licensed otherwise. A documentation on the license situation of dependencies can be found in the table below.

1.2.1 OFIQ License

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

1.2.2 License of dependencies

In the table the license situation of the files shipped with the OFIQ source is documented.

File/directory	Description	Reference	Original license
CMakeLists.txt	CMake file for building OFIQ	-	OFIQ license
README.md	Readme file	-	OFIQ license
LICENSE.md	File containing license information	-	OFIQ license
Version.txt	Contains OFIQ's current version information.	-	OFIQ license
cmake/	Folder containing cmake helper scripts	https://cmake.org/	OFIQ license
data/ofiq_config.jaxn	OFIQ's configuration file	-	OFIQ license
data/models/	Folder containing a single readme file; to this folder, model files are downloaded from the ISO portal when running one of the building scripts. Note, the readme file is subject to OFIQ's license. The license situation of the model files is documented separately in license files placed in the sub-directories after download.	-	-
data/tests/expected_results/expected_results.csv	CSV file with expected native quality scores and quality component values used for running conformance tests.	-	OFIQ license
data/tests/images/	Folder containing a single readme file; to this folder, conformance test images are downloaded from the ISO portal when running one of the building scripts. Note, the readme file is subject to OFIQ's license. The license situation of the image files is documented separately in a license file downloaded with the images.	-	-
conan/	Directory containing files that are used for the Conan package manager.	https://conan.io/	OFIQ license
OFIQlib/	Directory containing the OFIQ source code (including headers).	-	OFIQ license
doc/src/mainpage.h	Doxygen documentation of OFIQ	-	OFIQ license

File/directory	Description	Reference	Original license
doc/src/ofiq-doxygen.cfg	Configuration for building doxygen documentation. Has been generated by doxygen and was edited afterwards. May be affected by copyleft. Was used to generate doc/refman.pdf which does not, however, need to be linked with any software compilation using OFIQ.	https://www.doxygen.org/	mixed
doc/refman.pdf	Documentation of OFIQ. Generated by doxygen and LaTeX. The documentation does not need to be linked with any software compilation using OFIQ.	https://www.doxygen.org/ , https://www.latex-project.org/	mixed
scripts/build.cmd	Script for building OFIQ-Release on Windows; includes steps for installing packages via conan and downloading models and conformance test images from ISO portal.	-	OFIQ license
scripts/build_debug.cmd	Script for building OFIQ-Debug on Windows; includes steps for installing packages via conan and downloading models and conformance test images from ISO portal.	-	OFIQ license
scripts/build.sh	Script for building OFIQ-Release on Linux; includes steps for installing packages via conan and downloading models and conformance test images from ISO portal.	-	OFIQ license
scripts/build_debug.sh	Script for building OFIQ-Debug on Linux; includes steps for installing packages via conan and downloading models and conformance test images from ISO portal.	-	OFIQ license
scripts/conformance_tests.cmd	Runs conformance tests with OFIQ-Release on Windows	-	OFIQ license
scripts/conformance_tests_debug.cmd	Runs conformance tests with OFIQ-Debug on Windows	-	OFIQ license
scripts/conformance_tests.sh	Runs conformance tests with OFIQ-Release on Linux	-	OFIQ license
scripts/conformance_tests_debug.sh	Runs conformance tests with OFIQ-Debug on Linux	-	OFIQ license

File/directory	Description	Reference	Original license
testing/	Directory containing OFIQ source code running conformance tests	-	OFIQ license

1.3 Compilation

To build OFIQ you need to install Python with pip, cmake and conan.

- Python (version 3.10.12 or higher)
- [Download and install cmake](#) (version 3.26 or higher)
- [Download and install conan](#) (version 2.0.17)

1.3.1 Linux

The following has been tested on an Ubuntu 22.04 (64 bit) installation. Install necessary packages.

```
$ sudo apt-get install build-essential python3-pip liblapack-dev
```

To install cmake (in a version 3.26 or higher) use snap (and not apt) as follows.

```
$ sudo snap install cmake --classic
```

Conan is installed via Python with

```
pip install conan==2.0.17
```

In order to build OFIQ and installing all required packages via conan run the following.

```
$ cd <OFIQ-SOURCE>/scripts
$ sh build.sh
```

where <OFIQ-SOURCE> denotes the root folder of the OFIQ source files. This will create the following output.

file/directory	description
build/	Folder with the Linux build including the binaries OFIQSampleApp and libofiq_↵_lib.so.
build/conan/	Conan cache with packages downloaded.
install_x86_64_linux/	Folder with the installation including the binaries Release/bin/OFIQSampleApp, Release/lib/libofiq_lib.so, Release/lib/libonnxruntime.↵so.1.14.1, and the header files in Release/include/.
data/models/	Model files downloaded from the ISO portal during build process. (see Download model files).
data/tests/images/	Conformance test images downloaded from the ISO portal (see Download conformance test images).

1.3.2 Windows

The following has been tested on a Windows 10 (64 bit) installation using a **Python installation version 3.11.5** with pip package such that the `pip` command can be executed from the command prompt. Furthermore, an installation of **cmake version 3.29** has been used. As the compiler, **Microsoft's Visual Studio 2019** was used.

To install conan, run

```
$ pip install conan==2.0.17
```

from the command prompt.

In order to build OFIQ and install all required packages run the following.

```
$ cd <OFIQ-SOURCE>\scripts\  
$ .\build.cmd
```

where `<OFIQ-SOURCE>` denotes the root folder of the OFIQ source files.

This will create the following output.

file/directory	description
build\build_win\	Folder with the Visual Studio solution files placed and pre-compilation.
build\conan\	Conan cache with packages downloaded.
install_x86_64\	Folder with the OFIQ installation files. This includes the binaries <code>Release\bin\OFIQSampleApp</code> , <code>Release\bin\libofiq_lib.so</code> , <code>Release\bin\libonnxruntime.so.1.14.1</code> , and the header files in <code>Release\include\</code> .
data\models\	Model files downloaded from the ISO portal during build process (see Download model files).
data\tests\images\	Conformance test images downloaded from the ISO portal (see Download conformance test images).

1.3.3 Download model files

To run OFIQ, the model files from [the ISO portal](#) need to be downloaded and be placed in the `./data/models/` directory. This step is integrated in the cmake building process.

1.3.4 Download conformance test images

To run conformance tests, the conformance test images need to be downloaded from [the ISO portal](#) and be placed in the `./data/tests/images/` directory. This step is integrated in the cmake building process.

1.4 Running conformance tests

The conformance tests are executed by going to `<OFIQ-SOURCE>/scripts/` and run `conformance_↵tests.cmd` (Windows) or `conformance_tests.sh` (Linux).

1.5 Running the sample executable

In this section, we describe how to run the sample application of OFIQ after compilation (see [Compilation](#)). A documentation for the arguments that can be passed can be found [below](#).

1.5.1 Quality assessment for a single facial image

The sample application takes an images and outputs the computed quality assessments. For example, to output the quality assessments for one of the conformance test images using OFIQ's configuration (in `./data`), run the following commands on Linux.

```
$ cd <OFIQ-SOURCE>/install_x86_64_linux/Release/bin/
$ ./OFIQSampleApp -c ../../../../data/ofiq_config.jaxn -i
  ../../../../data/tests/images/b-01-smile.png
```

On Windows run the following commands.

```
$ cd <OFIQ-SOURCE>\install_x86_64\Release\bin
$ .\OFIQSampleApp -c ..\..\..\data\ofiq_config.jaxn -i
  ..\..\..\data\tests\images\b-01-smile.png
```

1.5.2 Quality assessment for multiple images

To reproduce the conformance test table given in Annex A of the ISO/IEC 29794-5 international standard for all conformance test images, run the following commands on Linux.

```
$ cd <OFIQ-SOURCE>/install_x86_64_linux/Release/bin/
$ ./OFIQSampleApp -c ..\..\..\data\ofiq_config.jaxn -i
  ..\..\..\data\tests\images\ -o table.csv
```

The result will be written in the file `<OFIQ-SOURCE>/install_x86_64_linux/Release/bin/table.csv`.

On Windows run the following commands.

```
$ cd <OFIQ-SOURCE>\install_x86_64\Release\bin\
$ .\OFIQSampleApp -c ..\..\..\data\ -i
  ..\..\..\data\tests\images\ -o table.csv
```

The result will be written in the file `<OFIQ-SOURCE>\install_x86_64\Release\bin\table.csv`.

1.5.3 Arguments

The usage pattern of the sample application is the following.

```
OFIQSampleApp
  -c <directory or file path>
  [-cf <config file name>]
  -i <directory or image file path>
  [-o <csv file path>]
```

The following table documents the usage of the sample application.

flag	argument
-c	Path to a directory containing the file ofiq_config.jaxn or a path to a JAXN configuration file (see Configuration).
-cf	Name of the JAXN configuration file contained in the directory specified by the flag -c. Must be omitted if -c specifies a path to a file.
-i	Path to a directory containing facial images or a path to a facial image file. If a directory path is specified, all images in PNG and JPEG format will be processed.
-o	Path to a CSV file to where the quality assessment is written. If -o is not specified, the output is written to the standard output.

1.6 Configuration

In this section, we describe the configuration file for OFIQ. OFIQ uses a JSON-like configuration based on the [taoJSON](#) library. Using taoJSON, OFIQ reads its configuration from a [JAXN](#)-formatted file.

A minimal configuration working with OFIQ looks as follows.

```
{
  "config": {
    "detector": "ssd",
    "landmarks": "ADNet",
    "measures": [
      "UnifiedQualityScore"
    ],
    "params": {
      "detector": {
        "ssd": {
          "model_path": "models/face_detection/ssd_facedetect.caffemodel",
          "prototxt_path": "models/face_detection/ssd_facedetect.prototxt.txt",
          "confidence_thr": 0.4,
          "min_rel_face_size": 0.01,
          "padding": 0.2
        }
      },
      "landmarks": {
        "ADNet": {
          "model_path": "models/face_landmark_estimation/ADNet.onnx"
        }
      },
      "measures": {
        "UnifiedQualityScore": {
          "model_path": "models/unified_quality_score/magface_iresnet50_norm.onnx"
        },
        "HeadPose": {
          "model_path": "models/head_pose_estimation/mb1_120x120.onnx"
        },
        "FaceOcclusionSegmentation": {
          "model_path": "models/face_occlusion_segmentation/face_occlusion_segmentation_ort.onnx"
        },
        "FaceParsing": {
          "model_path": "models/face_parsing/bisenet_400.onnx"
        }
      }
    }
  }
}
```

OFIQ's C/C++ library provides the class [Configuration](#) which is responsible for reading and managing JAXN configurations.

Note that the model paths are specified as paths relative to the directory of the JAXN configuration file. We assume that the file above is stored in <OFIQ-SOURCE>/data.

1.6.1 Configuration of the face detector

The face detector (SSD) must be configured explicitly:

```
{
  "config": {
    "detector": "ssd",
    ...
  }
}
```

Additionally, the path to the model file and other parameters need to be configured:

```
{
  ...
  "params": {
    "detector": {
      "ssd": {
        "model_path": "models/face_detection/ssd_facedetect.caffemodel",
        "prototxt_path": "models/face_detection/ssd_facedetect.prototxt.txt",
        "confidence_thr": 0.4,
        "min_rel_face_size": 0.01,
        "padding": 0.2
      }
    },
    ...
  }
}
```

A documentation on the parameters are given in the following table.

Parameter	Description
model_path	path to the SSD model file in CAFFE format
prototxt_path	path to SSD's CAFFE prototype file
confidence_thr	minimum value for the confidence the detected faces; detected faces with a lower confidence are discarded. Note, the specified value 0.4 (fixed for OFIQ) has been determined experimentally.
min_rel_face_size	the minimum width of the face bounding boxes relative to the width w of the input image; detected faces, with a bounding box width smaller than $\text{min_rel_face_size} * w$ are discarded. Note, the specified value 0.01 (fixed for OFIQ) has been determined experimentally.
padding	horizontal and vertical padding of the original image prior face detection. Note, the specified value 0.2 (fixed for OFIQ) has been determined experimentally.

1.6.2 Configuration of the landmark extractor

The face landmark extractor (ADNet) must be configured explicitly:

```
{
  "config": {
    ...
    "landmarks": "ADNet",
    ...
  }
}
```

Additionally, the path to the ADNet model file in ONNX format needs to be configured:

```
{
  ...
  "params": {
    ...
    "landmarks": {
      "ADNet": {
        "model_path": "models/face_landmark_estimation/ADNet.onnx"
      }
    },
    ...
  }
}
```

1.6.3 Other required configurations

As suggested by the minimal configuration file given in [Configuration](#), there are model files that need to be configured and their configurations cannot be omitted. These model files are detailed in the following table and shall be configured in the "config"."measures" environment.

Algorithm	Description
HeadPose	Head pose angles are pre-processed and used by some measures; therefore, the measure shall be configured. The path to the 3DDFAV2 model file in ONNX format should be set using the <code>model_path</code> key.
FaceOcclusionSegmentation	Face occlusion segmentation pre-processing used by some measures assessing occlusion prevention. The path to the FaceExtraction model file in ONNX format should be set using the <code>model_path</code> key. NOTE: The OFIQ development team has been permitted by the FaceExtraction authors for inclusion of the model in OFIQ without any restrictions; therefore, the referenced ONNX model file is subject to the OFIQ license agreement.
FaceParsing	Face parsing is pre-processed and used by some measures; therefore, the measure shall be configured (even if no measure is requested that uses the pre-processing result). The path to the BiSeNet model file in ONNX format should be set using the <code>model_path</code> key.

1.6.4 Requesting measures

OFIQ implements a variety of measures for assessing properties of a facial image. For a measure to be executed by OFIQ, it must be explicitly requested. For example, to only request the unified quality score measure, one can request it as follows.

```
{
  "config": {
```

```

...
"measures": [
  "UnifiedQualityScore"
],
...
}
}

```

At least one measure must be requested. An empty request list will result in OFIQ throwing an error. A full list of requestable measures and its *measure keys* can be found in the table of the [default configuration section](#).

1.6.5 Default configuration

OFIQ is the reference implementation for the ISO/IEC 29794-5 standard. To reproduce the conformance tests of the ISO/IEC 29794-5 standard one should use the (default) configuration provided by the file `<OFIQ←SOURCE>/data/ofiq_config.jaxn`; other configurations can be used; however, the resulting outputs of the quality assessment may not comply with the ISO/IEC 29794-5 standard.

The entries of the default configuration are documented in the following table. Details on the algorithms can be found in the ISO/IEC 29794-5 document. Details on the implementations can be found in the OFIQ source code. Note, the QAA identifiers listed in the table are defined in ISO/IEC 29794-5.

QAA identifier	description	config key	request key	configuration parameters	supports quality mapping config? - see details here
-	Face detector	"config">"params": "detector"	-	see here	-
-	Face landmark estimator	"config">"params": "landmarks"	-	see here	-
-	Face parsing	"config". "params". "measures". "FaceParsing"	-	see here	-
-	Face occlusion segmentation	"config". "params". "measures". "Face←Occlusion←Segmentation"	-	see here	-
-	Landmarked region	"config". "params". "measures". "FaceRegion"	-	alpha: is 0 per default and only used for internal purposes	-
0x41	Unified quality score	"config". "params". "measures". "Unified←QualityScore"	"config". "measures". "Unified←QualityScore"	model_←path: Path to an iResNet50 model file in ONNX format	yes
0x42	Background uniformity	"config". "params". "measures". "Background←Uniformity"	"config". "measures". "Background←Uniformity"	none	yes

0x43	Illumination uniformity	"config". "params". "measures". "Illumination↔ Uniformity"	"config". "measures". "Illumination↔ Uniformity"	none	yes
0x44	Luminance brightness	"config". "params". "measures". "Luminance"	"config". "measures". "Luminance"	none	yes
0x45	Luminance contrast	"config". "params". "measures". "Luminance"	"config". "measures". "Luminance"	none	yes
0x46	Absence of under-exposure	"config". "params". "measures". "Under↔ Exposure↔ Prevention"	"config". "measures". "Under↔ Exposure↔ Prevention"	none	yes
0x47	Absence of over-exposure	"config". "params". "measures". "Over↔ Exposure↔ Prevention"	"config". "measures". "Over↔ Exposure↔ Prevention"	none	yes
0x48	Pixel intensity variation	"config". "params". "measures". "Dynamic↔ Range"	"config". "measures". "Dynamic↔ Range"	none	yes
0x49	Sharpness	"config". "params". "measures". "Sharpness"	"config". "measures". "Sharpness"	model_↔ path: Path to the random forest model file	yes
0x4A	Absence of compression artifacts	"config". "params". "measures". "No↔ Compression↔ Artifacts"	"config". "measures". "No↔ Compression↔ Artifacts"	model_↔ path: Path to OFIQ's com- pression artifact CNN in ONNX format	yes
0x4B	Colour natural-ity	"config". "params". "measures". "NaturalColour"	"config". "measures". "NaturalColour"	none	yes
0x4C	Face unique-ness	"config". "params". "measures". "SingleFace↔ Present"	"config". "measures". "SingleFace↔ Present"	none	no
0x4D	Eyes openness	"config". "params". "measures". "EyesOpen"	"config". "measures". "EyesOpen"	none	yes
0x4E	Mouth closed-ness	"config". "params". "measures". "MouthClosed"	"config". "measures". "MouthClosed"	none	yes

0x4F	Eyes visibility	"config". "params". "measures". "EyesVisible"	"config". "measures". "EyesVisible"	none	yes
0x50	Mouth occlusion prevention	"config". "params". "measures". "Mouth↔ Occlusion↔ Prevention"	"config". "measures". "Mouth↔ Occlusion↔ Prevention"	none	yes
0x51	Face occlusion prevention	"config". "params". "measures". "Face↔ Occlusion↔ Prevention"	"config". "measures". "Face↔ Occlusion↔ Prevention"	none	yes
0x52	Inter-eye distance length	"config". "params". "measures". "InterEye↔ Distance"	"config". "measures". "InterEye↔ Distance"	none	yes
0x53	Size of the head in the image	"config". "params". "measures". "HeadSize"	"config". "measures". "HeadSize"	none	yes - the argument to the quality mapping is $\ x - 0.45\ $ where x is the native quality score
0x54	Leftward crop of the face image	"config">"params". "measures". "CropOfThe↔ FacelImage". "Leftward↔ CropOfThe↔ FacelImage"	"config". "measures". "CropOfThe↔ FacelImage"	none	yes
0x55	Rightward crop of the face image	"config">"params". "measures". "CropOfThe↔ FacelImage". "Rightward↔ CropOfThe↔ FacelImage"	"config". "measures". "CropOfThe↔ FacelImage"	none	yes
0x56	Upward crop of the face image	"config">"params". "measures". "CropOfThe↔ FacelImage". "UpwardCrop↔ OfTheFace↔ Image"	"config". "measures". "CropOfThe↔ FacelImage"	none	yes
0x57	Downward crop of the face image	"config">"params". "measures". "CropOfThe↔ FacelImage". "Downward↔ CropOfThe↔ FacelImage"	"config". "measures". "CropOfThe↔ FacelImage"	none	yes

0x58	Pose angle yaw frontal alignment	"config">-	"config". "measures". "HeadPose"	none	no
0x59	Pose angle pitch frontal alignment	-	"config". "measures". "HeadPose"	none	no
0x5A	Pose angle roll frontal alignment	-	"config". "measures". "HeadPose"	none	no
0x5B	Expression neutrality	"config">"params" "measures". "Expression↔ Neutrality"	"config". "measures". "Expression↔ Neutrality"	cnn_model↔ _path1: Path to the CNN model <i>enet</i> ↔ <i>b0_8_best</i> ↔ <i>vgaf_embed</i> ↔ <i>_zeroed.onnx</i> derived from here in ONNX format cnn_model↔ _path2: Path to the CNN model <i>enet_b2</i> ↔ <i>8_embed</i> ↔ <i>zeroed.</i> ↔ <i>onnx</i> derived from here in ONNX format. adaboost↔ _model↔ path: Path to the AdaBoost classifier model file <i>hse</i> ↔ <i>1_2_C</i> ↔ <i>adaboost.</i> ↔ <i>yml.gz</i> from here	yes
0x5C	Absence of head coverings	"config">"params" "measures". "NoHead↔ Covering"	"config". "measures". "NoHead↔ Covering"	threshold - threshold between 0 and 1-/td>	no

1.6.6 Configuration of the quality mapping

Each measure implemented in OFIQ outputs a pair of values. The first value is called *native quality score*. The second value is called *quality component value* which is an integer between 0 (worst quality) and 100 (best quality). The quality component value and is derived from the *native quality score* using a mapping function. Whether this mapping function can be configured for the measure is stated in the table of section [Default configuration](#).

Note, the OFIQ library implements hard-coded default quality mappings as a fallback.

A configurable quality mapping has the form of

$$Q(h, a, s, x, x_0, w) = h \cdot (a + s \cdot \text{sigmoid}(x, x_0, w))$$

where

$$\text{sigmoid}(x, x_0, w) = (1 + \exp((x_0 - x)/w))^{-1}.$$

Note, x is the native quality score which is mapped to the quality component value. The other symbols denote parameters that can be configured (see the example at the end of this section).

parameter	description	default value
"h"	scale factor	100
"a"	constant shift	0
"s"	signed weight for sigmoid part	1
"x0"	center point within sigmoid function; the default value has been chosen arbitrarily and should specified when a mapping is configured.	4
"w"	divisor within the sigmoid function; the default value has been chosen arbitrarily and should specified when a mapping is configured.	0.7
"round"	applies the compiler's native rounding function (<code>std::round</code>) such that only integer values are used as the quality value	true

All parameters are optional and can be omitted. In this case, the default value is chosen. Note, if a mapping results in a value not within 0 and 100, then a clipping is applied choosing the value 0 or 100 being closest to the mapped value.

For example, OFIQ's configuration for the background uniformity measure looks as follows

```
{
  "config" :
  ...
  "params": {
    ...
    "BackgroundUniformity": {
      "Sigmoid" : {
        "h": 190,
        "a": 1,
        "s": -1,
        "x0": 10,
        "w" : 100,
        "round": true
      }
    }
    ...
  }
}
```

1.7 C++ API

To use OFIQ in a C++ application one needs to include the following header file.

```
include <ofiq_lib.h>
```

In the following, we assume that the namespace `OFIQ` and `OFIQ_LIB` are used.

```
using namespace OFIQ;
using namespace OFIQ_LIB;
```

An `OFIQ` instance is initialized using the `Interface` class as follows.

```
// Get implementation pointer
auto implPtr = Interface::getImplementation();
// Initialization
auto ret = implPtr->initialize(configDir, configFile);
```

Here `configDir` is a `std::string`-representation of the path to the directory in which a JAXN configuration file of name `configFile` is stored - as documented in the [configuration section](#). Note, that the path can be absolute or relative to the path of the current working directory.

The input image is read by using the `readImage` function as follows

```
Image image;
ReturnStatus retStatus = readImage(imagePath, image);
```

where `imagePath` is a `std::string`-representation of a path to an image file. The representation is written to the `image` object of type `Image`.

To compute the quality assessments, run

```
FaceImageQualityAssessment assessment;
ReturnStatus retStatus = implPtr->vectorQuality(image, assessment);
```

A successful computation is indicated by `retStatus.code` if it is of value `ReturnCode::Success`. Then the assessment result is stored in a `FaceImageQualityAssessment` struct object. The obtained `FaceImageQualityAssessment` object has a `std::map` member which, for a specified `QualityMeasure` key, returns the `QualityMeasureResult`. A `QualityMeasureResult` struct object contains the native quality score stored in the `rawScore` member and the quality component value stored in the `scalar` member. Note, both members are encoded as a `double` values although the `scalar` member should (on successful quality measure computation) be an integer value between 0 and 100. To check whether a `QualityMeasureResult` has been computed successfully, one checks if its `code` member agrees with the value `QualityMeasureReturnCode::Success`.

1.8 Implementation and pre-processing workflow

Quality assessment is controlled by the implementation of the `OFIQImpl` class. A shared pointer to an `OFIQImpl` object is returned by the `Interface::getImplementation()` function. The implementation needs to be initialized once using the `OFIQImpl::initialize()` function. Note, the `OFIQImpl::initialize()` function loads all model files as specified in the input configuration into memory; thus, one should avoid creating repeated instances of the `OFIQImpl`.

After successful initialization, the implementation object can be used and one can repeatedly invoke the `OFIQImpl::vectorQuality()` function to assess the quality of a series of facial images.

The internal workflow of the `OFIQImpl::vectorQuality()` implementation is as follows.

1. Pre-processing of the input image using the `OFIQImpl::performPreprocessing()` function.
 - (a) Face detection implemented by `SSDFaceDetector::UpdateFaces()`.
 - (b) Pose estimation implemented by `HeadPose3DDFAV2::updatePose()`.
 - (c) Landmark extraction implemented by `ADNetFaceLandmarkExtractor::updateLandmarks()`.
 - (d) Facial alignment implemented by `OFIQImpl::alignFaceImage()`.
 - (e) Face parsing implemented by `FaceParsing::UpdateMask()`.
 - (f) Face occlusion segmentation implemented by `FaceOcclusionSegmentation::UpdateMask()`.
2. Quality assessment using the `Executor::ExecuteAll()` function: For all requested measures
 - (a) its `Execute()`
 - (b) and then its `SetQualityMeasure()` functions are invoked.

1.9 Release notes

This is OFIQ [Version 1.0.0-RC \(2024-03-15\)](#). The following table lists all measures and its implementation provided by this release of OFIQ. Details on the configuration and on requesting measures can be found [here](#). Note, the QAA identifiers listed in the table are defined in ISO/IEC 29794-5.

QAA identifier	Description	OFIQ implementation reference
0x41	MagFace-based unified quality score measure.	UnifiedQualityScore
0x42	Gradient-based background uniformity.	BackgroundUniformity
0x43	Illumination uniformity by summing up the minima of the histograms of the left and the right side of the face.	IlluminationUniformity
0x44	Luminance mean measure computed from the luminance histogram	Luminance
0x45	Luminance variance measure computed from the luminance histogram	Luminance
0x46	Under-exposure prevention by computing the proportion of low-intensity pixels in the luminance image to assess the absence of under-exposure	UnderExposurePrevention
0x47	Over-exposure prevention by computing the proportion of high-intensity pixels in the luminance image to assess the absence of over-exposure	OverExposurePrevention
0x48	Dynamic range computed from the luminance histogram.	DynamicRange
0x49	Sharpness assessment based on a random forest classifier trained by the OFIQ development team.	Sharpness
0x4A	Assessment of the absence of compression artifact (both JPEG and JPEG2000) based on a CNN trained by the OFIQ development team.	CompressionArtifacts
0x4B	Assessment of the naturalness of the colour based on the conversion of the RGB presentation of the image to the CIELAB colour space.	NaturalColour
0x4C	Assessment of the uniqueness of the most dominant face detected by comparing its size with the size of the second largest face detected	SingleFacePresent
0x4D	Eyes openness assessment based on computing eyes aspect ratio from eye landmarks	EyesOpen

0x4E	Mouth closed assessment based on computing a ratio from mouth landmarks	MouthClosed
0x4F	Eyes visibility assessment by measuring the coverage of the eye visibility zone with the result of face occlusion segmentation computed during pre-processing.	EyesVisible
0x50	Assessment of the absence of mouth occlusion by measuring the coverage of the mouth region from mouth landmarks with the result of face occlusion segmentation computed on pre-processing.	MouthOcclusionPrevention
0x51	Assessment of the absence of face occlusion by measuring the coverage of the landmarked region with the result of face occlusion segmentation computed during pre-processing.	FaceOcclusionPrevention
0x52	Inter-eye distance assessment based on computing the Euclidean length of eyes' centres and multiplication with the secant of the yaw angle computed during pre-processing.	InterEyeDistance
0x53	Size of the head based on computing the height of the face computed from facial landmarks with the height of the image.	HeadSize
0x54	Leftward crop of the face image	CropOfTheFaceImage
0x55	Rightward crop of the face image	CropOfTheFaceImage
0x56	Downward crop of the face image	CropOfTheFaceImage
0x57	Upward crop of the face image	CropOfTheFaceImage
0x58	Pose angle yaw frontal alignment based on the 3DDFAV2 .	HeadPose
0x59	Pose angle pitch frontal alignment based on the 3DDFAV2	HeadPose
0x5A	Pose angle roll frontal alignment based on the 3DDFAV2	HeadPose
0x5B	Expression neutrality estimation based on a fusion of HSEMotion with Efficient-↔ Expression-Neutrality-Estimation .	ExpressionNeutrality
0x5C	Assessment of the absence of head coverings by counting the pixels being labeled as head covers in the mask output by the face parsing computed during pre-processing.	NoHeadCoverings

1.9.1 Changelog

1.9.1.1 Version 1.0.0-RC (2024-03-15)

Initial release of OFIQ's release candidate providing the measures described in the [Release notes](#)

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

cv	OpenCV's namespace	31
OFIQ	Namespace for OFIQ API	31
OFIQ_LIB	Namespace for OFIQ implementations	35
OFIQ_LIB::modules	45
OFIQ_LIB::modules::detectors	Provides face detector implementations	46
OFIQ_LIB::modules::landmarks	Provides implementations of a landmark extractors	46
OFIQ_LIB::modules::landmarks::adnet	Namespace for ADNet-specific landmarks	49
OFIQ_LIB::modules::measures	Provides measures implemented in OFIQ	52
OFIQ_LIB::modules::poseEstimators	Provides implementation of a head pose estimator	54
OFIQ_LIB::modules::segmentations	Provides segmentation-related implementations	55

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

OFIQ::BoundingBox	63
OFIQ_LIB::Configuration	68
std::exception	
OFIQ_LIB::OFIQError	150
OFIQ_LIB::modules::measures::Executor	77
OFIQ_LIB::FaceDetectorInterface	86
OFIQ_LIB::modules::detectors::SSDFaceDetector	190
OFIQ::FaceImageQualityAssessment	88
OFIQ_LIB::FaceLandmarkExtractorInterface	89
OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor	57
OFIQ::FaceLandmarks	91
OFIQ_LIB::modules::landmarks::FaceMeasures	92
OFIQ::Image	118
OFIQ::Interface	122
OFIQ_LIB::OFIQImpl	152
OFIQ_LIB::modules::landmarks::LandmarkPair	125
OFIQ::LandmarkPoint	126
OFIQ_LIB::modules::measures::Measure	130
OFIQ_LIB::modules::measures::BackgroundUniformity	59
OFIQ_LIB::modules::measures::CompressionArtifacts	65
OFIQ_LIB::modules::measures::CropOfTheFacelImage	73
OFIQ_LIB::modules::measures::DynamicRange	75
OFIQ_LIB::modules::measures::ExpressionNeutrality	79
OFIQ_LIB::modules::measures::EyesOpen	82
OFIQ_LIB::modules::measures::EyesVisible	84
OFIQ_LIB::modules::measures::FaceOcclusionPrevention	96
OFIQ_LIB::modules::measures::HeadPose	108
OFIQ_LIB::modules::measures::HeadSize	114
OFIQ_LIB::modules::measures::IlluminationUniformity	116
OFIQ_LIB::modules::measures::InterEyeDistance	120
OFIQ_LIB::modules::measures::Luminance	128
OFIQ_LIB::modules::measures::MouthClosed	138
OFIQ_LIB::modules::measures::MouthOcclusionPrevention	140
OFIQ_LIB::modules::measures::NaturalColour	142

OFIQ_LIB::modules::measures::NoHeadCoverings	148
OFIQ_LIB::modules::measures::OverExposurePrevention	160
OFIQ_LIB::modules::measures::Sharpness	182
OFIQ_LIB::modules::measures::SingleFacePresent	188
OFIQ_LIB::modules::measures::UnderExposurePrevention	193
OFIQ_LIB::modules::measures::UnifiedQualityScore	195
OFIQ_LIB::modules::measures::MeasureFactory	137
OFIQ_LIB::NeuronalNetworkContainer	146
ONNXRuntimeSegmentation	157
OFIQ_LIB::modules::landmarks::PartExtractor	162
Point2f	163
OFIQ_LIB::Point2i	164
OFIQ_LIB::PoseEstimatorInterface	165
OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2	110
OFIQ::QualityMeasureResult	167
OFIQ::ReturnStatus	168
OFIQ_LIB::SegmentationExtractorInterface	170
OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation	98
OFIQ_LIB::modules::segmentations::FaceParsing	102
OFIQ_LIB::Session	172
OFIQ_LIB::modules::measures::SigmoidParameters	186

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor	Class implementing the FaceLandmarkExtractorInterface interface	57
OFIQ_LIB::modules::measures::BackgroundUniformity	Implementation of the background uniformity measure	59
OFIQ::BoundingBox	Data structure for describing bounding boxes, e.g. the face region of the faces found by a face detector	63
OFIQ_LIB::modules::measures::CompressionArtifacts	Implementation of the no compression artifacts measure	65
OFIQ_LIB::Configuration	Configuration class	68
OFIQ_LIB::modules::measures::CropOfTheFacelImage	Implementation of the crop of the face image measure	73
OFIQ_LIB::modules::measures::DynamicRange	Implementation of the dynamic range measure	75
OFIQ_LIB::modules::measures::Executor	This class takes care of the computation of the measures activated	77
OFIQ_LIB::modules::measures::ExpressionNeutrality	Provides a class implementing the expression neutrality measure	79
OFIQ_LIB::modules::measures::EyesOpen	Implementation of the eyes open measure	82
OFIQ_LIB::modules::measures::EyesVisible	Implementation of the eyes visible measure	84
OFIQ_LIB::FaceDetectorInterface	Provides the interface class to the face detector implementations	86
OFIQ::FacelImageQualityAssessment	Data structure storing the results of the different measurement computations	88
OFIQ_LIB::FaceLandmarkExtractorInterface	Implements the base class for the face landmark extractors	89
OFIQ::FaceLandmarks	Data structure for storing facial landmarks	91
OFIQ_LIB::modules::landmarks::FaceMeasures	Provides static functions doing computations with landmarks	92
OFIQ_LIB::modules::measures::FaceOcclusionPrevention	Implementation of the face occlusion prevention measure	96

OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation	Class managing the separation of facial parts not occluded by non-facial parts from other parts	98
OFIQ_LIB::modules::segmentations::FaceParsing	Class managing the separation of facial parts not occluded by non-facial parts from other parts	102
OFIQ_LIB::modules::measures::HeadPose	Implementation of head pose measures	108
OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2	Implementation of a head pose estimator	110
OFIQ_LIB::modules::measures::HeadSize	Implementation of the head size measure	114
OFIQ_LIB::modules::measures::IlluminationUniformity	Implementation of the illumination uniformity measure	116
OFIQ::Image	Struct representing a single image	118
OFIQ_LIB::modules::measures::InterEyeDistance	Implementation of the inter-eye distance measure	120
OFIQ::Interface	The interface to FACE QA implementation	122
OFIQ_LIB::modules::landmarks::LandmarkPair	Data container for storing pairs of landmarks	125
OFIQ::LandmarkPoint	Data structure to describe the x and y coordinate of a landmark	126
OFIQ_LIB::modules::measures::Luminance	Implementation of two luminance measures	128
OFIQ_LIB::modules::measures::Measure	Base class for measures implemented in OFIQ	130
OFIQ_LIB::modules::measures::MeasureFactory	Measure factor class	137
OFIQ_LIB::modules::measures::MouthClosed	Implementation of the mouth closed measure	138
OFIQ_LIB::modules::measures::MouthOcclusionPrevention	Implementation of the mouth occlusion prevention measure	140
OFIQ_LIB::modules::measures::NaturalColour	Implementation of the natural colour measure	142
OFIQ_LIB::NeuralNetworkContainer	Neural network container for OFIQ's preprocessing steps	146
OFIQ_LIB::modules::measures::NoHeadCoverings	Implementation of the no head covering measure	148
OFIQ_LIB::OFIQError	Implementation of a custom exception	150
OFIQ_LIB::OFIQImpl	Implementation of the OFIQ_LIB	152
ONNXRuntimeSegmentation	Helper class to manage the ONNXRuntime session object	157
OFIQ_LIB::modules::measures::OverExposurePrevention	Implementation of the over-exposure prevention measure	160
OFIQ_LIB::modules::landmarks::PartExtractor	Class that provides helper methods for the administration of landmarks	162
Point2f	Representation of a point with floating point arithmetics	163
OFIQ_LIB::Point2i	Representation of a point with integer arithmetics	164
OFIQ_LIB::PoseEstimatorInterface	Implementation of the base class for integrating pose estimation algorithms capable of estimating three head orientation angles (yaw, pitch and roll) from a face image	165
OFIQ::QualityMeasureResult	Data structure to handle the results of a quality measure	167

OFIQ::ReturnStatus	A structure to contain information about a failure by the software under test	168
OFIQ_LIB::SegmentationExtractorInterface	Base class for the different implementation of segmentation algorithms	170
OFIQ_LIB::Session	172
OFIQ_LIB::modules::measures::Sharpness	Implementantation of the sharpness measure	182
OFIQ_LIB::modules::measures::SigmoidParameters	Parameters of the sigmoid function based quality mapping	186
OFIQ_LIB::modules::measures::SingleFacePresent	Implementation of the single face present measure	188
OFIQ_LIB::modules::detectors::SSDFaceDetector	Implementation of a face detector using the SSD face detector CNN	190
OFIQ_LIB::modules::measures::UnderExposurePrevention	Implementation of the under-exposure prevention measure	193
OFIQ_LIB::modules::measures::UnifiedQualityScore	Implementation of the unified quality measure	195

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

mainpage.h	This header file is for generating the doxygen documentation for OFIQ	199
ofiq_lib.h	Class describing the interface to the OFIQ	200
ofiq_lib_impl.h	Implementation of the OFIQ_LIB	201
ofiq_structs.h	PRovides several helper classes, enums and functions used in the OFIQ framework	203
AllDetectors.h	Provides the include statements to all classes derived from FaceDetectorInterface	208
detectors.h	Provides the interface class to the face detector implementations	209
opencv_ssd_face_detector.h	Implementation of a face detector using the SSD face detector CNN	210
adnet_FaceMap.h	Provides definitions of landmark indices to access specific parts of ADNet landmarks	211
adnet_landmarks.h	Provides the ADNetFaceLandmarkExtractor class	214
AllLandmarks.h	Provides the include statements to all classes derived from FaceLandmarkExtractorInterface	216
FaceMeasures.h	Provides a class implementing two luminance measures	216
FaceParts.h	PRovides several helper classes, enums and functions used in the OFIQ framework	218
landmarks.h	Provides the base class for the implementation of face landmark extractors	220
PartExtractor.h	Provides helper class for face landmark handling	221
AllMeasures.h	Provides all classes derived from the OFIQ_LIB::modules::measures::Measure class	223
BackgroundUniformity.h	Provides a class implementing the background uniformity measure	224
CompressionArtifacts.h	Provides a class implementing the no compression artifact measure	226
CropOfTheFaceImage.h	Provides a class implementing the crop of the face image measure	227

DynamicRange.h	Provides a class implementing the dynamic range measure	229
Executor.h	This class takes care of the computation of the measures activated	230
ExpressionNeutrality.h	Provides a class implementing the expression neutrality measure	231
EyesOpen.h	Provides a class implementing the eyes open measure	233
EyesVisible.h	Provides a class implementing the eyes visible measure	234
FaceOcclusionPrevention.h	Provides a class implementing the face occlusion prevention measure	235
HeadPose.h	Provides a class implementing head pose measures	237
HeadSize.h	Provides a class implementing the head size measure	238
IlluminationUniformity.h	Provides a class implementing the illumination uniformity measure	239
InterEyeDistance.h	Provides a class implementing the inter-eye distance measure	241
Luminance.h	Provides a class implementing two luminance measures	242
Measure.h	Provides the base class for all measures implemented in OFIQ	243
MeasureFactory.h	Provides a class for requesting creation of measure implementations	246
MouthClosed.h	Provides a class implementing the mouth closed measure	247
MouthOcclusionPrevention.h	Provides a class implementing the mouth occlusion prevention measure	248
NaturalColour.h	Provides a class implementing the natural colour measure	250
NoHeadCoverings.h	Provides a class implementing the no head covering measure	251
OverExposurePrevention.h	Provides a class implementing the background uniformity measure	252
Sharpness.h	Provides a class implementing the sharpness measure	254
SingleFacePresent.h	Provides a class implementing the single face present measure	255
UnderExposurePrevention.h	Provides a class implementing the under-exposure prevention measure	256
UnifiedQualityScore.h	Provides a class implementing the unified quality measure	258
AllPoseEstimators.h		259
HeadPose3DDFAV2.h	Provides a class implementing a head pose estimator based on https://github.com/cleardusk/3DDFA_V2	260
poseEstimators.h	Base class for the different implementation of pose estimation algorithms	261
FaceOcclusionSegmentation.h	Provides a class for segmenting the facial part not occluded by any non-facial parts from an image	263
FaceParsing.h	Provides a class implementing the face parsing pre-processing	264
ONNXRTSegmentation.h	Helper class to manage the ONNXRuntime session object	266

segmentations.h	Base class for the different implementation of segmentation algorithms	267
Configuration.h	Provides a configuration class for handling configurations	269
image_io.h	Provides helper functions for reading/writing images from/to disk	271
image_utils.h	Provides image utility functions such as color conversion, luminance computation etc	272
NeuronalNetworkContainer.h	274
OFIQError.h	Provides a class for the error handling within the QFIQ	275
Session.h	The session class is the data container used to distribute the image and additional data, including the data computed during the pre-processing	276
utils.h	Helper functions used by several classes	278

Chapter 6

Namespace Documentation

6.1 cv Namespace Reference

OpenCV's namespace.

6.1.1 Detailed Description

OpenCV's namespace.

6.2 OFIQ Namespace Reference

Namespace for OFIQ API.

Classes

- struct [BoundingBox](#)
Data structure for describing bounding boxes, e.g. the face region of the faces found by a face detector.
- struct [FacelImageQualityAssessment](#)
Data structure storing the results of the different measurement computations.
- struct [FaceLandmarks](#)
Data structure for storing facial landmarks.
- struct [Image](#)
Struct representing a single image.
- class [Interface](#)
The interface to FACE QA implementation.
- struct [LandmarkPoint](#)
Data structure to describe the x and y coordinate of a landmark.
- struct [QualityMeasureResult](#)
Data structure to handle the results of a quality measure.
- struct [ReturnStatus](#)
A structure to contain information about a failure by the software under test.

Typedefs

- using `QualityAssessments` = `std::map<QualityMeasure, QualityMeasureResult>`
Data structure that stores key-value pairs, with each entry representing a quality element and its value.
- using `Landmarks` = `std::vector<LandmarkPoint>`
container for a collection of landmarks, e.g. belonging to all the landmarks detected on a face image.

Enumerations

- enum class `ReturnCode` {
`Success` = 0 , `ImageReadingError` , `ImageWritingError` , `MissingConfigParamError` ,
`UnknownConfigParamError` , `FaceDetectionError` , `FaceLandmarkExtractionError` , `FaceOcclusionSegmentationError`
, `FaceParsingError` , `UnknownError` , `QualityAssessmentError` , `NotImplemented` }
Return codes for functions specified in this API.
- enum class `QualityMeasure` {
`UnifiedQualityScore` = 0x41 , `BackgroundUniformity` = 0x42 , `IlluminationUniformity` = 0x43 , `Luminance` =
-0x44 ,
`LuminanceMean` = 0x44 , `LuminanceVariance` = 0x45 , `UnderExposurePrevention` = 0x46 , `OverExposurePrevention`
= 0x47 ,
`DynamicRange` = 0x48 , `Sharpness` = 0x49 , `CompressionArtifacts` = 0x4a , `NaturalColour` = 0x4b ,
`SingleFacePresent` = 0x4c , `EyesOpen` = 0x4d , `MouthClosed` = 0x4e , `EyesVisible` = 0x4f ,
`MouthOcclusionPrevention` = 0x50 , `FaceOcclusionPrevention` = 0x51 , `InterEyeDistance` = 0x52 , `HeadSize`
= 0x53 ,
`CropOfTheFacelImage` = -0x54 , `LeftwardCropOfTheFacelImage` = 0x54 , `RightwardCropOfTheFacelImage` =
0x55 , `DownwardCropOfTheFacelImage` = 0x56 ,
`UpwardCropOfTheFacelImage` = 0x57 , `HeadPose` = -0x58 , `HeadPoseYaw` = 0x58 , `HeadPosePitch` = 0x59 ,
`HeadPoseRoll` = 0x5a , `ExpressionNeutrality` = 0x5b , `NoHeadCoverings` = 0x5c , `NotSet` = -1 }
Enums presenting the measure labels.
- enum class `QualityMeasureReturnCode` { `Success` = 0 , `FailureToAssess` , `NotInitialized` }
Return codes for QualityMeasureResult.
- enum class `FaceDetectorType` { `OPENCVSSD` , `NotSet` }
Enum describing the different face detector implementations.
- enum class `LandmarkType` { `LM_98` , `NotSet` }
Enum describing the different implementations of landmarks.

Functions

- `std::ostream & operator<<` (`std::ostream &s`, const `ReturnCode` &rc)

6.2.1 Detailed Description

Namespace for OFIQ API.

Namespace for OFIQ API.

6.2.2 Typedef Documentation

6.2.2.1 Landmarks

```
using OFIQ::Landmarks = std::vector<LandmarkPoint>
```

container for a collection of landmarks, e.g. belonging to all the landmarks detected on a face image.

6.2.2.2 QualityAssessments

```
using OFIQ::QualityAssessments = std::map<QualityMeasure, QualityMeasureResult>
```

Data structure that stores key-value pairs, with each entry representing a quality element and its value.

6.2.3 Enumeration Type Documentation

6.2.3.1 FaceDetectorType

```
enum class OFIQ::FaceDetectorType [strong]
```

Enum describing the different face detector implementations.

Enumerator

OPENCVSSD	face detector based on the ssd implementation in opencv.
NotSet	unknown face detector

6.2.3.2 LandmarkType

```
enum class OFIQ::LandmarkType [strong]
```

Enum describing the different implementations of landmarks.

Enumerator

LM_98	Landmarks extracted with the adnet detector.
NotSet	used for iterating through the enums.

6.2.3.3 QualityMeasure

```
enum class OFIQ::QualityMeasure [strong]
```

Enums presenting the measure labels.

Enumerator

UnifiedQualityScore	UnifiedQualityScore
BackgroundUniformity	BackgroundUniformity
IlluminationUniformity	IlluminationUniformity
Luminance	the common measure implementation for LuminanceMean, LuminanceVariance
LuminanceMean	LuminanceMean
LuminanceVariance	LuminanceVariance
UnderExposurePrevention	UnderExposurePrevention
OverExposurePrevention	OverExposurePrevention

Enumerator

DynamicRange	DynamicRange
Sharpness	Sharpness
CompressionArtifacts	CompressionArtifacts
NaturalColour	NaturalColour
SingleFacePresent	SingleFacePresent
EyesOpen	EyesOpen
MouthClosed	MouthClosed
EyesVisible	EyesVisible
MouthOcclusionPrevention	MouthOcclusionPrevention
FaceOcclusionPrevention	FaceOcclusionPrevention
InterEyeDistance	InterEyeDistance
HeadSize	HeadSize
CropOfTheFacelImage	CropOfTheFacelImage: common measure for {Left,Right,Up,Down}wardCropOfTheFacelImage
LeftwardCropOfTheFacelImage	LeftwardCropOfTheFacelImage
RightwardCropOfTheFacelImage	RightwardCropOfTheFacelImage
DownwardCropOfTheFacelImage	DownwardCropOfTheFacelImage
UpwardCropOfTheFacelImage	UpwardCropOfTheFacelImage
HeadPose	HeadPose
HeadPoseYaw	HeadPoseYaw
HeadPosePitch	HeadPosePitch
HeadPoseRoll	HeadPoseRoll
ExpressionNeutrality	ExpressionNeutrality
NoHeadCoverings	NoHeadCoverings
NotSet	unknown measure

6.2.3.4 QualityMeasureReturnCode

```
enum class OFIQ::QualityMeasureReturnCode [strong]
```

Return codes for QualityMeasureResult.

Enumerator

Success	Success
FailureToAssess	Unable to assess a quality measure
NotInitialized	Quality measure is not initialized

6.2.3.5 ReturnCode

```
enum class OFIQ::ReturnCode [strong]
```

Return codes for functions specified in this API.

Enumerator

Success	Success
ImageReadingError	Failed to read an image.
ImageWritingError	failed to write an image to disk.
MissingConfigParamError	A required config parameter is missing
UnknownConfigParamError	A required config parameter is missing
FaceDetectionError	Unable to detect a face in the image
FaceLandmarkExtractionError	Unable to extract landmarks from face
FaceOcclusionSegmentationError	Unable to extract occlusion segments from face
FaceParsingError	Unable to parse face
UnknownError	Catch-all error
QualityAssessmentError	Failure to generate a quality score on the input image
NotImplemented	Function is not implemented

6.2.4 Function Documentation

6.2.4.1 operator<<()

```
std::ostream & OFIQ::operator<< (
    std::ostream & s,
    const ReturnCode & rc ) [inline]
```

Output stream operator for a ReturnCode object.

6.3 OFIQ_LIB Namespace Reference

Namespace for OFIQ implementations.

Namespaces

- namespace [modules](#)

Classes

- class [Configuration](#)
Configuration class.
- class [FaceDetectorInterface](#)
Provides the interface class to the face detector implementations.
- class [FaceLandmarkExtractorInterface](#)
Implements the base class for the face landmark extractors.
- struct [NeuralNetworkContainer](#)
Neural network container for OFIQ's preprocessing steps.
- class [OFIQError](#)
Implementation of a custom exception.
- class [OFIQImpl](#)

Implementation of the OFIQ_LIB.

- struct [Point2i](#)
Representation of a point with integer arithmetics.
- class [PoseEstimatorInterface](#)
Implementation of the base class for integrating pose estimation algorithms capable of estimating three head orientation angles (yaw, pitch and roll) from a face image.
- class [SegmentationExtractorInterface](#)
Base class for the different implementation of segmentation algorithms.
- class [Session](#)

Typedefs

- using [ExposureRange](#) = std::array<int, 2>
- using [EulerAngle](#) = std::array<double, 3>

Functions

- [OFIQ_EXPORT OFIQ::ReturnStatus readImage](#) (const std::string &filename, [OFIQ::Image](#) &image)
Read image from disk.
- [OFIQ_EXPORT double ColorConvert](#) (double v)
Converts a color as specified in ISO/IEC 29794-5.
- [OFIQ_EXPORT double Cubic](#) (double x, double k, double eps)
Cubic flattening function.
- [OFIQ_EXPORT void ConvertBGRToCIELAB](#) (const cv::Mat &bgrImage, double &a, double &b)
Computes CIELAB values a^ and b^* from a BGR image.*
- [OFIQ_EXPORT cv::Mat GetLuminanceImageFromBGR](#) (const cv::Mat &bgrImage)
Converts a BGR image to the luminance image.
- [OFIQ_EXPORT void CalculateReferencePoints](#) (const [OFIQ::FaceLandmarks](#) &landmarks, [OFIQ::LandmarkPoint](#) &leftEyeCenter, [OFIQ::LandmarkPoint](#) &rightEyeCenter, double &interEyeDistance, double &eyeMouthDistance)
Computes the left eye center, the right eye center, the (planar) inter-eye-distance and the eye to mouth distance from facial landmarks.
- [OFIQ_EXPORT void CalculateRegionOfInterest](#) (cv::Rect &leftRegionOfInterest, cv::Rect &rightRegionOfInterest, const [OFIQ::LandmarkPoint](#) &leftEyeCenter, const [OFIQ::LandmarkPoint](#) &rightEyeCenter, const double interEyeDistance, const double eyeMouthDistance)
Extracts regions being of interest for some measures (e.g. NaturalColour).
- [OFIQ_EXPORT void GetNormalizedHistogram](#) (const cv::Mat &luminanceImage, const cv::Mat &maskImage, cv::Mat1f &histogram)
Computes the normalized histogram from a luminance image in 256 chunks.
- [OFIQ_EXPORT double CalculateExposure](#) (const [Session](#) &session, const [ExposureRange](#) &exposureRange)
Helper function for some measures.
- [OFIQ_EXPORT double ComputeBrightnessAspect](#) (const cv::Mat &luminanceImage, const cv::Mat &maskImage, const [ExposureRange](#) &exposureRange)
Helper function for some measures.
- [OFIQ_EXPORT void makeSquareBoundingBoxWithPadding](#) (const [OFIQ::BoundingBox](#) &i_bb, const cv::Mat &i_input_image, cv::Mat &o_output_image, [OFIQ::BoundingBox](#) &o_bb, [Point2i](#) &o_translation_vector)
Some computations, especially neural networks, need a squarred image as input. This funtion consumes a boundig box and an input image. The greater parameter of width or height is used to define the side length of the new squarred bounding box. The face will be centered in the bounding box. Padding is added if needed. The squarred bounding box is used generate a new cropped image, the o_output_image. Required translations are described by the translation vector o_translation_vector.

- [OFIQ_EXPORT OFIQ::BoundingBox makeSquareBoundingBox](#) (const [OFIQ::BoundingBox](#) &i_bb)
This function converts a non-squared bounding box into a squared one. The side length is defined by the greater one of height or width.
- [OFIQ_EXPORT size_t findLargestBoundingBox](#) (const std::vector< [OFIQ::BoundingBox](#) > &faceRects)
This function returns the position of the largest bounding box (largest in terms of area) from a vector of bounding boxes.
- [OFIQ_EXPORT cv::Mat copyToCvImage](#) (const [OFIQ::Image](#) &sourceImage, bool asGrayImage=false)
Convert images in OFIQ::Image format into the OpenCV cv::Mat format. The image can be converted from color to gray scale by setting the parameter asGrayImage to true.
- [OFIQ_EXPORT cv::Mat alignImage](#) (const [OFIQ::Image](#) &faceImage, const [OFIQ::FaceLandmarks](#) &faceLandmarks, [OFIQ::FaceLandmarks](#) &alignedFaceLandmarks, cv::Mat &transformationMatrix)
This function transforms a face image so that the position of the eyes, nose and mouth are roughly at a pre-defined position. Face alignment is the translation, rotation and scaling of the image to do this.
- [OFIQ_EXPORT void calculateEyeCenter](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, [Point2f](#) &leftEyeCenter, [Point2f](#) &rightEyeCenter)
Based on face landmarks the center of the left and right eye are computed.
- [OFIQ_EXPORT OFIQ::Image MakeGreyImage](#) (uint16_t width, uint16_t height)
This function generates a gray scaled image with the resolution passed by the call.
- [OFIQ_EXPORT float tmetric](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks)
Based on the provided landmarks this function computes the distance between the point between the eyes and the chin.
- [OFIQ_EXPORT void rotationMatrixToEulerAngles](#) (const cv::Mat &R, std::vector< double > &angles)
Based on a given rotation matrix this functions computes and returns the corresponding Euler angles.

6.3.1 Detailed Description

Namespace for OFIQ implementations.

Provides implementations in OFIQ.

Namespace for OFIQ implementations.

6.3.2 Typedef Documentation

6.3.2.1 EulerAngle

```
using OFIQ_LIB::EulerAngle = std::array<double, 3>
```

6.3.2.2 ExposureRange

```
using OFIQ_LIB::ExposureRange = std::array<int, 2>
```

6.3.3 Function Documentation

6.3.3.1 alignImage()

```
OFIQ_EXPORT cv::Mat OFIQ_LIB::alignImage (
    const OFIQ::Image & faceImage,
    const OFIQ::FaceLandmarks & faceLandmarks,
    OFIQ::FaceLandmarks & alignedFaceLandmarks,
    cv::Mat & transformationMatrix )
```

This function transforms a face image so that the position of the eyes, nose and mouth are roughly at a pre-defined position. Face alignment is the translation, rotation and scaling of the image to do this.

Parameters

<i>faceImage</i>	Input image.
<i>faceLandmarks</i>	Face landmarks, based on the face represented in the input image.
<i>alignedFaceLandmarks</i>	Face landmarks of the aligned face image.
<i>transformationMatrix</i>	Transformation matrix used to transform the landmarks.

Returns

cv::Mat Aligned face image with a resolution of 616x616.

6.3.3.2 CalculateExposure()

```
OFIQ_EXPORT double OFIQ_LIB::CalculateExposure (
    const Session & session,
    const ExposureRange & exposureRange )
```

Helper function for some measures.

The function is used by [UnderExposurePrevention](#) and [OverExposurePrevention](#) class. Details can be found in the ISO/IEC 29794-5 standard.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
<i>exposureRange</i>	Range of pixels for which the aspect is computed.

Returns

Exposure computed from the inputs.

6.3.3.3 calculateEyeCenter()

```
OFIQ_EXPORT void OFIQ_LIB::calculateEyeCenter (
    const OFIQ::FaceLandmarks & faceLandmarks,
    Point2f & leftEyeCenter,
    Point2f & rightEyeCenter )
```

Based on face landmarks the center of the left and right eye are computed.

Parameters

<i>faceLandmarks</i>	Input face landmarks.
<i>leftEyeCenter</i>	Point coordinates of the left eye center.
<i>rightEyeCenter</i>	Point coordinates of the right eye center.

6.3.3.4 CalculateReferencePoints()

```
OFIQ_EXPORT void OFIQ_LIB::CalculateReferencePoints (
    const OFIQ::FaceLandmarks & landmarks,
    OFIQ::LandmarkPoint & leftEyeCenter,
    OFIQ::LandmarkPoint & rightEyeCenter,
    double & interEyeDistance,
    double & eyeMouthDistance )
```

Computes the left eye center, the right eye center, the (planar) inter-eye-distance and the eye to mouth distance from facial landmarks.

Parameters

in	<i>landmarks</i>	Facial landmarks
out	<i>leftEyeCenter</i>	Left eye center computed from landmarks
out	<i>rightEyeCenter</i>	Right eye center computed from landmarks
out	<i>interEyeDistance</i>	Inter-eye distance computed from landmarks (does not consider the yaw angle).
out	<i>eyeMouthDistance</i>	Distance from the eyes' midpoint to the mouth.

6.3.3.5 CalculateRegionOfInterest()

```
OFIQ_EXPORT void OFIQ_LIB::CalculateRegionOfInterest (
    cv::Rect & leftRegionOfInterest,
    cv::Rect & rightRegionOfInterest,
    const OFIQ::LandmarkPoint & leftEyeCenter,
    const OFIQ::LandmarkPoint & rightEyeCenter,
    const double interEyeDistance,
    const double eyeMouthDistance )
```

Extracts regions being of interest for some measures (e.g. NaturalColour).

Details can be found in the ISO/IEC 29794-5 standard for the Natural colour measure.

Parameters

out	<i>leftRegionOfInterest</i>	Rectangular region corresponding to the left eye
out	<i>rightRegionOfInterest</i>	Rectangular region corresponding to the right eye
in	<i>leftEyeCenter</i>	Center of the left eye
in	<i>rightEyeCenter</i>	Center of the right eye
in	<i>interEyeDistance</i>	Planar inter-eye distance
in	<i>eyeMouthDistance</i>	Distance from the eyes' centers midpoint to the mouth

Returns

Applies a heuristic to estimate two regions being of interest for the natural colour measure.

6.3.3.6 ColorConvert()

```
OFIQ_EXPORT double OFIQ_LIB::ColorConvert (
    double v )
```

Converts a color as specified in ISO/IEC 29794-5.

Parameters

<i>v</i>	An intensity value between 0 (black) and 1 (white).
----------	---

Returns

If $v > 0.04045$, then $((v + 0.055)/1.055)^{2.4}$ is returned; otherwise, if $v \leq 0.04045$, then $v/12.92$ is returned.

6.3.3.7 ComputeBrightnessAspect()

```
OFIQ_EXPORT double OFIQ_LIB::ComputeBrightnessAspect (
    const cv::Mat & luminanceImage,
    const cv::Mat & maskImage,
    const ExposureRange & exposureRange )
```

Helper function for some measures.

The function is used by [UnderExposurePrevention](#) and [OverExposurePrevention](#) class. Details can be found in the ISO/IEC 29794-5 standard.

Parameters

<i>luminanceImage</i>	luminance image.
<i>maskImage</i>	The mask on which the aspect is computed
<i>exposureRange</i>	Range of pixels for which the aspect is computed.

Returns

Brightness aspect computed from the inputs.

6.3.3.8 ConvertBGRToCIELAB()

```
OFIQ_EXPORT void OFIQ_LIB::ConvertBGRToCIELAB (
    const cv::Mat & bgrImage,
    double & a,
    double & b )
```

Computes CIELAB values a^* and b^* from a BGR image.

Parameters

in	<i>bgrImage</i>	BGR image
out	<i>a</i>	CIELAB value a^*
out	<i>b</i>	CIELAB value b^*

6.3.3.9 copyToCvImage()

```
OFIQ_EXPORT cv::Mat OFIQ_LIB::copyToCvImage (
    const OFIQ::Image & sourceImage,
    bool asGrayImage = false )
```

Convert images in OFIQ::Image format into the OpenCV cv::Mat format. The image can be converted from color to gray scale by setting the parameter asGrayImage to true.

Parameters

<i>sourceImage</i>	Input image.
<i>asGrayImage</i>	Switch for adding gray scale conversion.

Returns

cv::Mat Input image in cv::Mat format.

6.3.3.10 Cubic()

```
OFIQ_EXPORT double OFIQ_LIB::Cubic (
    double x,
    double k,
    double eps )
```

Cubic flattening function.

Parameters

<i>x</i>	Argument
<i>k</i>	Argument
<i>eps</i>	Argument ϵ

Returns

If $x \leq \epsilon$, then $(k \cdot x + 16)/116$ is returned; otherwise, if $x > \epsilon$, then $\sqrt[3]{x}$ is returned.

6.3.3.11 findLargestBoundingBox()

```
OFIQ_EXPORT size_t OFIQ_LIB::findLargestBoundingBox (
    const std::vector< OFIQ::BoundingBox > & faceRects )
```

This function returns the position of the largest bounding box (largest in terms of area) from a vector of bounding boxes.

Parameters

<i>faceRects</i>	Vector containing bounding boxes.
------------------	-----------------------------------

Returns

size_t Position of the largest bounding box in the vector.

6.3.3.12 GetLuminanceImageFromBGR()

```
OFIQ_EXPORT cv::Mat OFIQ_LIB::GetLuminanceImageFromBGR (
    const cv::Mat & bgrImage )
```

Converts a BGR image to the luminance image.

The conversion is specified in the ISO/IEC 29794-5 standard and uses the function [ColorConvert\(\)](#) .

Parameters

<i>bgrImage</i>	BGR image
-----------------	-----------

Returns

Luminance image.

6.3.3.13 GetNormalizedHistogram()

```
OFIQ_EXPORT void OFIQ_LIB::GetNormalizedHistogram (
    const cv::Mat & luminanceImage,
    const cv::Mat & maskImage,
    cv::Mat1f & histogram )
```

Computes the normalized histogram from a luminance image in 256 chunks.

Parameters

in	<i>luminanceImage</i>	Luminance image as returned by GetLuminanceImageFromBGR() .
in	<i>maskImage</i>	The histogram is computed on pixels where the values of maskImage are non-zero.
out	<i>histogram</i>	Array of length 256 where the histogram is stored.

6.3.3.14 MakeGreyImage()

```
OFIQ_EXPORT OFIQ::Image OFIQ_LIB::MakeGreyImage (
    uint16_t width,
    uint16_t height )
```

This function generates a gray scaled image with the resolution passed by the call.

Parameters

<i>width</i>	Width of the generated image.
<i>height</i>	Height of the generated image.

Returns

OFIQ::Image Generated gray scaled image.

6.3.3.15 makeSquareBoundingBox()

```
OFIQ_EXPORT OFIQ::BoundingBox OFIQ_LIB::makeSquareBoundingBox (
    const OFIQ::BoundingBox & i_bb )
```

This function converts a non-squared bounding box into a squared one. The side length is defined by the greater one of height or width.

Parameters

<i>i_bb</i>	Input bounding box.
-------------	---------------------

Returns

OFIQ::BoundingBox Squarred bounding box.

6.3.3.16 makeSquareBoundingBoxWithPadding()

```
OFIQ_EXPORT void OFIQ_LIB::makeSquareBoundingBoxWithPadding (
    const OFIQ::BoundingBox & i_bb,
    const cv::Mat & i_input_image,
    cv::Mat & o_output_image,
    OFIQ::BoundingBox & o_bb,
    Point2i & o_translation_vector )
```

Some computations, especially neural networks, need a squared image as input. This function consumes a bounding box and an input image. The greater parameter of width or height is used to define the side length of the new squared bounding box. The face will be centered in the bounding box. Padding is added if needed. The squared bounding box is used to generate a new cropped image, the `o_output_image`. Required translations are described by the translation vector `o_translation_vector`.

Parameters

<i>i_bb</i>	Initial bounding box.
<i>i_input_image</i>	Input image.
<i>o_output_image</i>	Cropped output image. Cropping is based on the computed squared bounding box.
<i>o_bb</i>	Squared bounding box.
<i>o_translation_vector</i>	Translation vector.

6.3.3.17 readImage()

```
OFIQ_EXPORT OFIQ::ReturnStatus OFIQ_LIB::readImage (
    const std::string & filename,
    OFIQ::Image & image )
```

Read image from disk.

Parameters

in	<i>filename</i>	Path and file name of the image being read from disk.
out	<i>image</i>	Reference to the image object where the data is loaded to.

Returns

OFIQ::ReturnStatus

6.3.3.18 rotationMatrixToEulerAngles()

```
OFIQ_EXPORT void OFIQ_LIB::rotationMatrixToEulerAngles (
    const cv::Mat & R,
    std::vector< double > & angles )
```

Based on a given rotation matrix this functions computes and returns the corresponding Euler angles.

Parameters

<i>R</i>	Input rotation matrix
<i>angles</i>	Container with the computed Euler angles for [x,y,z] axis

6.3.3.19 tmetric()

```
OFIQ_EXPORT float OFIQ_LIB::tmetric (
    const OFIQ::FaceLandmarks & faceLandmarks )
```

Based on the provided landmarks this function computes the distance between the point between the eyes and the chin.

Parameters

<i>faceLandmarks</i>	Input face landmarks.
----------------------	-----------------------

Returns

float Computed distance.

6.4 OFIQ_LIB::modules Namespace Reference

Namespaces

- namespace [detectors](#)
Provides face detector implementations.
- namespace [landmarks](#)
Provides implementations of a landmark extractors.

- namespace [measures](#)
Provides measures implemented in OFIQ.
- namespace [poseEstimators](#)
Provides implementation of a head pose estimator.
- namespace [segmentations](#)
Provides segmentation-related implementations.

6.5 OFIQ_LIB::modules::detectors Namespace Reference

Provides face detector implementations.

Classes

- class [SSDFaceDetector](#)
Implementation of a face detector using the SSD face detector CNN.

6.5.1 Detailed Description

Provides face detector implementations.

6.6 OFIQ_LIB::modules::landmarks Namespace Reference

Provides implementations of a landmark extractors.

Namespaces

- namespace [adnet](#)
Namespace for ADNet-specific landmarks.

Classes

- class [ADNetFaceLandmarkExtractor](#)
Class implementing the [FaceLandmarkExtractorInterface](#) interface.
- class [FaceMeasures](#)
Provides static functions doing computations with landmarks.
- struct [LandmarkPair](#)
Data container for storing pairs of landmarks.
- class [PartExtractor](#)
Class that provides helper methods for the administration of landmarks.

Typedefs

- using `LandmarkId` = int
Type definition of a landmark index.
- using `LandmarkIds` = std::vector<`LandmarkId`>
Type definition of a list of landmark indices.
- using `FaceMap` = std::map<`FaceParts`, `LandmarkIds`>
Type definition of a face map to access landmark indices for a queried face part.
- using `LandmarkIdPair` = std::array<`LandmarkId`, 2>
Type definition for a pair of landmark index.
- using `LandmarkIdPairs` = std::vector<`LandmarkIdPair`>
Type definition for a list of landmark index pairs.
- using `FacePairMap` = std::map<`FaceParts`, `LandmarkIdPairs`>
Structure defining pairs of landmark indices.

Enumerations

- enum class `FaceParts` {
`LEFT_EYE`, `RIGHT_EYE`, `LEFT_EYE_CORNERS`, `RIGHT_EYE_CORNERS`,
`MOUTH_OUTER`, `MOUTH_INNER`, `FACE_CONTOUR`, `MOUTH_CENTER`,
`CHIN`, `NOSETIP`, `FOREHEAD` }
Enumeration of facial landmark parts.

6.6.1 Detailed Description

Provides implementations of a landmark extractors.

Provides implementations for computations with landmarks.

Provides implementations related to facial landmarks.

6.6.2 Typedef Documentation

6.6.2.1 FaceMap

```
using OFIQ_LIB::modules::landmarks::FaceMap = std::map<FaceParts, LandmarkIds>
```

Type definition of a face map to access landmark indices for a queried face part.

6.6.2.2 FacePairMap

```
using OFIQ_LIB::modules::landmarks::FacePairMap = std::map<FaceParts, LandmarkIdPairs>
```

Structure defining pairs of landmark indices.

6.6.2.3 LandmarkId

```
using OFIQ_LIB::modules::landmarks::LandmarkId = int
```

Type definition of a landmark index.

6.6.2.4 LandmarkIdPair

```
using OFIQ_LIB::modules::landmarks::LandmarkIdPair = std::array<LandmarkId, 2>
```

Type definition for a pair of landmark index.

6.6.2.5 LandmarkIdPairs

```
using OFIQ_LIB::modules::landmarks::LandmarkIdPairs = std::vector<LandmarkIdPair>
```

Type definition for a list of landmark index pairs.

6.6.2.6 LandmarkIds

```
using OFIQ_LIB::modules::landmarks::LandmarkIds = std::vector<LandmarkId>
```

Type definition of a list of landmark indices.

6.6.3 Enumeration Type Documentation

6.6.3.1 FaceParts

```
enum class OFIQ_LIB::modules::landmarks::FaceParts [strong]
```

Enumeration of facial landmark parts.

Enumerator

LEFT_EYE	left as seen on the image, it's the persons right eye
RIGHT_EYE	right as seen on the image, it's the persons left eye
LEFT_EYE_CORNERS	two landmarks - outer, inner corner
RIGHT_EYE_CORNERS	two landmarks - outer, inner corner
MOUTH_OUTER	outer landmarks of mouth
MOUTH_INNER	inner landmarks of mouth
FACE_CONTOUR	contour of the face
MOUTH_CENTER	center of the mouth
CHIN	chin
NOSETIP	nosetip
FOREHEAD	forehead

6.7 OFIQ_LIB::modules::landmarks::adnet Namespace Reference

Namespace for ADNet-specific landmarks.

Variables

- const [LandmarkIds leftEye](#) {60,61,62,63,64,65,66,67}
Landmark indices (ADNet) of the left eye.
- const [LandmarkIds rightEye](#) {68,69,70,71,72,73,74,75}
Landmark indices (ADNet) of the right eye.
- const [LandmarkIds leftEyeCorners](#) {60,64}
Landmark indices (ADNet) of the left eyes' corners.
- const [LandmarkIds rightEyeCorners](#) {68,72}
Landmark indices (ADNet) of the right eyes' corners.
- const [LandmarkIds nosetip](#) {54}
Landmark index (ADNet) of the nose tip.
- const [LandmarkIds mouthOuter](#) {76,77,78,79,80,81,82,83,84,85,86,87}
Landmark indices (ADNet) on the mouth's outer contour.
- const [LandmarkIds mouthInner](#) {88,89,90,91,92,93,94,95}
Landmark indices (ADNet) on the mouth's inner lip borders.
- const [LandmarkIds contour](#) {0,1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20,21,22,23,24,25,26,27,28,29,30,31,32}
Landmark indices (ADNet) of the face contour.
- const [LandmarkIds forehead](#) {}
Landmark indices (ADNet) of the forehead (empty for ADNet).
- const [LandmarkIds chin](#) {16}
Landmark index (ADNet) of the chin.
- const [landmarks::FaceMap FaceMap](#)
ADNets face map definition.
- const [LandmarkIdPairs pairsLeftEye](#)
Pair indices of landmarks (ADNet) for the left eye.
- const [LandmarkIdPairs pairsRightEye](#)
Landmark index pairs (ADNet) of landmarks for the right eye.
- const [LandmarkIdPairs pairsInnerLip](#)
Landmark index pairs (ADNet) of inner lip pairs.
- const [LandmarkIdPairs pairsMouthCenter](#)
Landmark index pair (ADNet) of the inner mouth (lips) center.
- const [landmarks::FacePairMap FacePairMap](#)
ADNets face pair map definition.

6.7.1 Detailed Description

Namespace for ADNet-specific landmarks.

6.7.2 Variable Documentation

6.7.2.1 chin

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::chin {16}
```

Landmark index (ADNet) of the chin.

6.7.2.2 contour

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::contour {0,1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18}
```

Landmark indices (ADNet) of the face contour.

6.7.2.3 FaceMap

```
const landmarks::FaceMap OFIQ_LIB::modules::landmarks::adnet::FaceMap
```

Initial value:

```
{
  {FaceParts::LEFT_EYE,      leftEye      },
  {FaceParts::RIGHT_EYE,    rightEye     },
  {FaceParts::LEFT_EYE_CORNERS, leftEyeCorners},
  {FaceParts::RIGHT_EYE_CORNERS, rightEyeCorners},
  {FaceParts::MOUTH_OUTER,  mouthOuter  },
  {FaceParts::MOUTH_INNER,  mouthInner  },
  {FaceParts::FACE_CONTOUR, contour     },
  {FaceParts::CHIN,        chin         },
  {FaceParts::NOSETIP,     nosetip     },
  {FaceParts::FOREHEAD,    forehead     }
}
```

ADNets face map definition.

6.7.2.4 FacePairMap

```
const landmarks::FacePairMap OFIQ_LIB::modules::landmarks::adnet::FacePairMap
```

Initial value:

```
{
  {FaceParts::LEFT_EYE,    pairsLeftEye  },
  {FaceParts::RIGHT_EYE,   pairsRightEye },
  {FaceParts::MOUTH_INNER, pairsInnerLip  },
  {FaceParts::MOUTH_CENTER, pairsMouthCenter}
}
```

ADNets face pair map definition.

6.7.2.5 forehead

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::forehead {}
```

Landmark indices (ADNet) of the forehead (empty for ADNet).

6.7.2.6 leftEye

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::leftEye {60,61,62,63,64,65,66,67}
```

Landmark indices (ADNet) of the left eye.

The left eye is defined as seen on the image; it is actually the person's right eye (physically).

6.7.2.7 leftEyeCorners

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::leftEyeCorners {60,64}
```

Landmark indices (ADNet) of the left eyes' corners.

6.7.2.8 mouthInner

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::mouthInner {88,89,90,91,92,93,94,95}
```

Landmark indices (ADNet) on the mouth's inner lip borders.

6.7.2.9 mouthOuter

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::mouthOuter {76,77,78,79,80,81,82,83,84,85,86,87}
```

Landmark indices (ADNet) on the mouth's outer contour.

6.7.2.10 nosetip

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::nosetip {54}
```

Landmark index (ADNet) of the nose tip.

6.7.2.11 pairsInnerLip

```
const LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsInnerLip
```

Initial value:

```
{
    {89, 95},
    {90, 94},
    {91, 93}
}
```

Landmark index pairs (ADNet) of inner lip pairs.

Useful to measure closedness of mouth.

6.7.2.12 pairsLeftEye

```
const LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsLeftEye
```

Initial value:

```
{
    {61, 67},
    {62, 66},
    {63, 65}
}
```

Pair indices of landmarks (ADNet) for the left eye.

Useful to measure eye openness.

6.7.2.13 pairsMouthCenter

```
const LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsMouthCenter
```

Initial value:

```
{  
    {90, 94}  
}
```

Landmark index pair (ADNet) of the inner mouth (lips) center.

Useful to measure closedness of mouth.

6.7.2.14 pairsRightEye

```
const LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsRightEye
```

Initial value:

```
{  
    {69, 75},  
    {70, 74},  
    {71, 73}  
}
```

Landmark index pairs (ADNet) of landmarks for the right eye.

Useful to measure eye openness.

6.7.2.15 rightEye

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::rightEye {68,69,70,71,72,73,74,75}
```

Landmark indices (ADNet) of the right eye.

The right eye is defined as seen on the image; it is actually the person's left eye (physically).

6.7.2.16 rightEyeCorners

```
const LandmarkIds OFIQ_LIB::modules::landmarks::adnet::rightEyeCorners {68,72}
```

Landmark indices (ADNet) of the right eyes' corners.

6.8 OFIQ_LIB::modules::measures Namespace Reference

Provides measures implemented in OFIQ.

Classes

- class [BackgroundUniformity](#)
Implementation of the background uniformity measure.
- class [CompressionArtifacts](#)
Implementation of the no compression artifacts measure.
- class [CropOfTheFaceImage](#)
Implementation of the crop of the face image measure.
- class [DynamicRange](#)
Implementation of the dynamic range measure.
- class [Executor](#)
This class takes care of the computation of the measures activated.
- class [ExpressionNeutrality](#)
Provides a class implementing the expression neutrality measure.
- class [EyesOpen](#)
Implementation of the eyes open measure.
- class [EyesVisible](#)
Implementation of the eyes visible measure.
- class [FaceOcclusionPrevention](#)
Implementation of the face occlusion prevention measure.
- class [HeadPose](#)
Implementation of head pose measures.
- class [HeadSize](#)
Implementation of the head size measure.
- class [IlluminationUniformity](#)
Implementation of the illumination uniformity measure.
- class [InterEyeDistance](#)
Implementation of the inter-eye distance measure.
- class [Luminance](#)
Implementation of two luminance measures.
- class [Measure](#)
Base class for measures implemented in OFIQ.
- class [MeasureFactory](#)
Measure factor class.
- class [MouthClosed](#)
Implementation of the mouth closed measure.
- class [MouthOcclusionPrevention](#)
Implementation of the mouth occlusion prevention measure.
- class [NaturalColour](#)
Implementation of the natural colour measure.
- class [NoHeadCoverings](#)
Implementation of the no head covering measure.
- class [OverExposurePrevention](#)
Implementation of the over-exposure prevention measure.
- class [Sharpness](#)
Implementation of the sharpness measure.
- struct [SigmoidParameters](#)
Parameters of the sigmoid function based quality mapping.
- class [SingleFacePresent](#)
Implementation of the single face present measure.
- class [UnderExposurePrevention](#)
Implementation of the under-exposure prevention measure.
- class [UnifiedQualityScore](#)
Implementation of the unified quality measure.

Functions

- void [log](#) (const std::string_view &msg)
Logging function for writing debug messages to std::cout.

Variables

- static const bool [execLogActive](#) = false
This variable enables logging to std::cout for debug purposes. By default the logging is switched off.

6.8.1 Detailed Description

Provides measures implemented in OFIQ.

6.8.2 Function Documentation

6.8.2.1 log()

```
void OFIQ_LIB::modules::measures::log (
    const std::string_view & msg )
```

Logging function for writing debug messages to std::cout.

Parameters

<i>msg</i>	Message to be logged.
------------	-----------------------

6.8.3 Variable Documentation

6.8.3.1 execLogActive

```
const bool OFIQ_LIB::modules::measures::execLogActive = false [static]
```

This variable enables logging to std::cout for debug purposes. By default the logging is switched off.

6.9 OFIQ_LIB::modules::poseEstimators Namespace Reference

Provides implementation of a head pose estimator.

Classes

- class [HeadPose3DDFAV2](#)
Implementation of a head pose estimator.

6.9.1 Detailed Description

Provides implementation of a head pose estimator.

6.10 OFIQ_LIB::modules::segmentations Namespace Reference

Provides segmentation-related implementations.

Classes

- class [FaceOcclusionSegmentation](#)
Class managing the separation of facial parts not occluded by non-facial parts from other parts.
- class [FaceParsing](#)
Class managing the separation of facial parts not occluded by non-facial parts from other parts.

Enumerations

- enum class [SegmentClassLabels](#) {
background , skin , l_brow , r_brow ,
l_eye , r_eye , eye_g , l_ear ,
r_ear , ear_r , nose , mouth ,
u_lip , l_lip , neck , neck_l ,
cloth , hair , hat , face }
Enum class of the different face regions that can be segmented.

6.10.1 Detailed Description

Provides segmentation-related implementations.

Namespace for implementations related to facial segmentations.

6.10.2 Enumeration Type Documentation

6.10.2.1 SegmentClassLabels

```
enum class OFIQ_LIB::modules::segmentations::SegmentClassLabels [strong]
```

Enum class of the different face regions that can be segmented.

Enumerator

background	background label
skin	skin label
l_brow	left eye brow
r_brow	right eye brow
l_eye	left eye
r_eye	right eye brow

Enumerator

eye_g	eye glasses
l_ear	left ear
r_ear	right eye brow
ear_r	earring
nose	nose
mouth	mouth
u_lip	upper lip
l_lip	lower lip
neck	neck
neck_l	necklace
cloth	clothing
hair	hair
hat	head covering
face	face

Chapter 7


Class Documentation

7.1 OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor Class Reference

Class implementing the [FaceLandmarkExtractorInterface](#) interface.

```
#include <adnet_landmarks.h>
```

Inheritance diagram for OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor:



Public Member Functions

- [ADNetFaceLandmarkExtractor](#) (const [Configuration](#) &config)
Constructor.
- [~ADNetFaceLandmarkExtractor](#) () override
Destructor.

Public Member Functions inherited from [OFIQ_LIB::FaceLandmarkExtractorInterface](#)

- virtual [~FaceLandmarkExtractorInterface](#) ()=default
Destructor.
- [OFIQ::FaceLandmarks](#) [extractLandmarks](#) ([OFIQ_LIB::Session](#) &session)
Public method to extract landmarks from the image passed in the session object.

Protected Member Functions

- [OFIQ::FaceLandmarks](#) [updateLandmarks](#) ([OFIQ_LIB::Session](#) &session) override
Computes landmarks of the face detected in the session.

Private Attributes

- `std::unique_ptr< ADNetFaceLandmarkExtractorImpl >` [landmarkExtractor](#)
Encapsulated implementation class.

7.1.1 Detailed Description

Class implementing the [FaceLandmarkExtractorInterface](#) interface.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 ADNetFaceLandmarkExtractor()

```
OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor::ADNetFaceLandmarkExtractor (
    const Configuration & config ) [explicit]
```

Constructor.

Parameters

<i>config</i>	Configuration object
---------------	----------------------

7.1.2.2 ~ADNetFaceLandmarkExtractor()

```
OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor::~~ADNetFaceLandmarkExtractor ( )
[override]
```

Destructor.

7.1.3 Member Function Documentation

7.1.3.1 updateLandmarks()

```
OFIQ::FaceLandmarks OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor::updateLandmarks
(
    OFIQ\_LIB::Session & session ) [override], [protected], [virtual]
```

Computes landmarks of the face detected in the session.

The landmarks are computed using ADNet.

Parameters

<i>session</i>	Session object containing preprocessing results used by the function to compute the landmarks.
----------------	--

Returns

Facial landmarks.

Implements [OFIQ_LIB::FaceLandmarkExtractorInterface](#).

7.1.4 Member Data Documentation**7.1.4.1 landmarkExtractor**

```
std::unique_ptr<ADNetFaceLandmarkExtractorImpl> OFIQ_LIB::modules::landmarks::ADNetFace↔
LandmarkExtractor::landmarkExtractor [private]
```

Encapsulated implementation class.

The documentation for this class was generated from the following file:


- [adnet_landmarks.h](#)

7.2 OFIQ_LIB::modules::measures::BackgroundUniformity Class Reference

Implementation of the background uniformity measure.

```
#include <BackgroundUniformity.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::BackgroundUniformity:

**Public Member Functions**

- [BackgroundUniformity](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses uniformity of the background.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Attributes

- `uint16_t m_target_height = 292`
The aligned image and the face parsing mask is brought to an image of the target height before gradient computations and assessment is applied.
- `uint16_t m_target_width = 354`
The aligned image and the face parsing mask is brought to an image of the target width before gradient computations and assessment is applied.
- `uint16_t m_crop_left = 62`
Crop from the left side of the aligned image (returned by `OFIQ_LIB::Session::getAlignedFace()`) before scaling to the target dimension is applied.
- `uint16_t m_crop_right = 62`
Crop from the right side of the aligned image (returned by `OFIQ_LIB::Session::getAlignedFace()`) before scaling to the target dimension is applied.
- `uint16_t m_crop_top = 0`
Crop from the top of the aligned image (returned by `OFIQ_LIB::Session::getAlignedFace()`) before scaling to the target dimension is applied.
- `uint16_t m_crop_bottom = 210`
Crop from the bottom of the aligned image (returned by `OFIQ_LIB::Session::getAlignedFace()`) before scaling to the target dimension is applied.
- `uint16_t m_erosion_kernel_size = 4`
Size of the erosion kernel applied to the background as per `OFIQ_LIB::modules::segmentations::FaceParsing` to reduce the risk that background uniformity estimation is applied to part of the subject.

Additional Inherited Members

Protected Member Functions inherited from `OFIQ_LIB::modules::measures::Measure`

- `void AddSigmoid (OFIQ::QualityMeasure measure, const SigmoidParameters &defaultValues)`
Reads sigmoid-function based quality mapping from the configuration.
- `void AddSigmoid (const std::string &key, SigmoidParameters defaultValues)`
Reads sigmoid-function based quality mapping from the configuration.
- `double ExecuteScalarConversion (OFIQ::QualityMeasure measure, double rawValue)`
Maps a native quality score to a quality component value.
- `double ExecuteScalarConversion (const std::string &key, double rawValue)`
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from `OFIQ_LIB::modules::measures::Measure`

- `static double Sigmoid (double x, double x0, double w)`
Sigmoid function.

Protected Attributes inherited from `OFIQ_LIB::modules::measures::Measure`

- `const Configuration & configuration`
Reference to the configuration with which the measure constructor has been invoked.

7.2.1 Detailed Description

Implementation of the background uniformity measure.

Uniformity of the background is measured on basis of the mean of the gradients computed on the background as per face parsing (see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).

7.2.2 Constructor & Destructor Documentation

7.2.2.1 BackgroundUniformity()

```
OFIQ_LIB::modules::measures::BackgroundUniformity::BackgroundUniformity (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which the measure related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results, computed by the OFIQImpl::performPreprocessing() .

7.2.3 Member Function Documentation

7.2.3.1 Execute()

```
void OFIQ_LIB::modules::measures::BackgroundUniformity::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Assesses uniformity of the background.

Assessment of the background uniformity is done by computing the mean of the background as per face parsing (see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() .
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.2.4 Member Data Documentation

7.2.4.1 m_crop_bottom

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_crop_bottom = 210 [private]
```

Crop from the bottom of the aligned image (returned by [OFIQ_LIB::Session::getAlignedFace\(\)](#)) before scaling to the target dimension is applied.

7.2.4.2 m_crop_left

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_crop_left = 62 [private]
```

Crop from the left side of the aligned image (returned by [OFIQ_LIB::Session::getAlignedFace\(\)](#)) before scaling to the target dimension is applied.

7.2.4.3 m_crop_right

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_crop_right = 62 [private]
```

Crop from the right side of the aligned image (returned by [OFIQ_LIB::Session::getAlignedFace\(\)](#)) before scaling to the target dimension is applied.

7.2.4.4 m_crop_top

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_crop_top = 0 [private]
```

Crop from the top of the aligned image (returned by [OFIQ_LIB::Session::getAlignedFace\(\)](#)) before scaling to the target dimension is applied.

7.2.4.5 m_erosion_kernel_size

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_erosion_kernel_size = 4 [private]
```

Size of the erosion kernel applied to the background as per [OFIQ_LIB::modules::segmentations::FaceParsing](#) to reduce the risk that background uniformity estimation is applied to part of the subject.

7.2.4.6 m_target_height

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_target_height = 292 [private]
```

The aligned image and the face parsing mask is brought to an image of the target height before gradient computations and assessment is applied.

7.2.4.7 m_target_width

```
uint16_t OFIQ_LIB::modules::measures::BackgroundUniformity::m_target_width = 354 [private]
```

The aligned image and the face parsing mask is brought to an image of the target width before gradient computations and assessment is applied.

The documentation for this class was generated from the following file:

- [BackgroundUniformity.h](#)

7.3 OFIQ::BoundingBox Struct Reference

Data structure for describing bounding boxes, e.g. the face region of the faces found by a face detector.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [BoundingBox](#) ()=default
Default constructor.
- [BoundingBox](#) (int16_t *xleft*, int16_t *ytop*, int16_t *width*, int16_t *height*, [FaceDetectorType](#) *i_faceDetector*)
Parameterized constructor.

Public Attributes

- int16_t [xleft](#) { -1 }
leftmost point on head, typically subject's right ear value must be on [0, imageWidth-1]
- int16_t [ytop](#) { -1 }
high point of head, typically top of hair; value must be on [0, imageHeight-1]
- int16_t [width](#) { -1 }
bounding box width
- int16_t [height](#) { -1 }
bounding box height
- [FaceDetectorType](#) [faceDetector](#) = [FaceDetectorType::NotSet](#)
Description of the face detector used.

7.3.1 Detailed Description

Data structure for describing bounding boxes, e.g. the face region of the faces found by a face detector.

7.3.2 Constructor & Destructor Documentation

7.3.2.1 BoundingBox() [1/2]

```
OFIQ::BoundingBox::BoundingBox ( ) [default]
```

Default constructor.

7.3.2.2 BoundingBox() [2/2]

```
OFIQ::BoundingBox::BoundingBox (
    int16_t xleft,
    int16_t ytop,
    int16_t width,
    int16_t height,
    FaceDetectorType i_faceDetector ) [inline]
```

Parameterized constructor.

Parameters

<i>xleft</i>	x coordinate of the upper left point of the bounding box.
<i>ytop</i>	y coordinate of the upper left point of the bounding box.
<i>width</i>	width of the bounding box.
<i>height</i>	height of the bounding box.
<i>i_faceDetector</i>	used face detector.

7.3.3 Member Data Documentation

7.3.3.1 faceDetector

`FaceDetectorType OFIQ::BoundingBox::faceDetector = FaceDetectorType::NotSet`

Description of the face detector used.

7.3.3.2 height

```
int16_t OFIQ::BoundingBox::height { -1 }
```

bounding box height

7.3.3.3 width

```
int16_t OFIQ::BoundingBox::width { -1 }
```

bounding box width

7.3.3.4 xleft

```
int16_t OFIQ::BoundingBox::xleft { -1 }
```

leftmost point on head, typically subject's right ear value must be on [0, imageWidth-1]

7.3.3.5 ytop

```
int16_t OFIQ::BoundingBox::ytop { -1 }
```

high point of head, typically top of hair; value must be on [0, imageHeight-1]

The documentation for this struct was generated from the following file:


- [ofiq_structs.h](#)

7.4 OFIQ_LIB::modules::measures::CompressionArtifacts Class Reference

Implementation of the no compression artifacts measure.

```
#include <CompressionArtifacts.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::CompressionArtifacts:



Public Member Functions

- [CompressionArtifacts](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses absence of compression artifacts.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Attributes

- uint16_t [m_crop](#)
Top, right, left, and bottom margin by which the aligned image is cropped.
- uint16_t [m_dim](#)
Target dimension of cropped image being scaled before input to the CNN .
- [ONNXRuntimeSegmentation](#) [m_onnxRuntimeEnv](#)
Manages CNN estimations.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.4.1 Detailed Description

Implementation of the no compression artifacts measure.

Assessment of the absence of compression artifact (both JPEG and JPEG2000) based on a CNN trained by the OFIQ development team.

7.4.2 Constructor & Destructor Documentation

7.4.2.1 CompressionArtifacts()

```
OFIQ_LIB::modules::measures::CompressionArtifacts::CompressionArtifacts (
    const Configuration & configuration,
    Session & session )
```

Constructor.

The configuration parameter must contain the following entry:

- `params.measures.CompressionArtifacts.model_path`: Path to the CNN model file in ONNX format.

The following entries can (but do not need to) be configured.

- `params.measures.CompressionArtifacts.dim`: If configured, the value must be 248 which corresponds to the dimension of the CNN's input layer; other values will result in an error being thrown when OFIQ's CNN is invoked.
- `params.measures.CompressionArtifacts.crop`: Top, right, bottom, and left margin by which the aligned input image will be cropped before being scaled to the target dimension input of the CNN.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

Exceptions

<i>OFIQ_LIB::OFIQError</i>	if no valid model path is configured.
----------------------------	---------------------------------------

7.4.3 Member Function Documentation**7.4.3.1 Execute()**

```
void OFIQ_LIB::modules::measures::CompressionArtifacts::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses absence of compression artifacts.

Assessment of the absence of compression artifact (both JPEG and JPEG2000) based on a CNN trained by the OFIQ development team.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.4.4 Member Data Documentation**7.4.4.1 m_crop**

```
uint16_t OFIQ_LIB::modules::measures::CompressionArtifacts::m_crop [private]
```

Top, right, left, and bottom margin by which the aligned image is cropped.

The value can be configured by passing a corresponding configuration to the constructor.

Warning

The value should be 184 such that an aligned input image of dimension 616 x 616 is cropped to an image of dimension 248 x 248.

7.4.4.2 m_dim

```
uint16_t OFIQ_LIB::modules::measures::CompressionArtifacts::m_dim [private]
```

Target dimension of cropped image being scaled before input to the CNN .

The cropped image is scaled to the dimension m_dim x m_dim. The value can be configured by passing a corresponding configuration to the constructor.

Warning

The value should be 248; if configured differently, do not expect that the cropped image can be successfully be passed to the CNN.

7.4.4.3 m_onnxRuntimeEnv

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::measures::CompressionArtifacts::m_onnxRuntimeEnv [private]
```

Manages CNN estimations.

The documentation for this class was generated from the following file:

- [CompressionArtifacts.h](#)

7.5 OFIQ_LIB::Configuration Class Reference

Configuration class.

```
#include <Configuration.h>
```

Public Member Functions

- [Configuration](#) (const std::string &configDir, const std::string &configFilename)
Constructor.
- bool [GetBool](#) (const std::string &key, bool &value) const
Accesses a boolean configuration.
- bool [GetString](#) (const std::string &key, std::string &value) const
Accesses a string configuration.
- bool [GetNumber](#) (const std::string &key, double &value) const
Accesses a double configuration.
- bool [GetStringList](#) (const std::string &key, std::vector< std::string > &value) const
Accesses an array of strings configured.
- bool [GetBool](#) (const std::string &key) const
Accesses a boolean configuration.
- std::string [GetString](#) (const std::string &key) const
Accesses a string configuration.
- double [GetNumber](#) (const std::string &key) const
Accesses a double configuration.
- std::string [getDataDir](#) () const
Access configuration directory.
- void [SetDataDir](#) (std::string dataDir)
Sets the configuration directory.

Private Attributes

- `std::map< std::string, tao::json::value, std::less<> >` [parameters](#)
Map holding all configuration that can be accessed using a string key.
- `std::filesystem::path` [m_dataDir](#)
Path to the configuration directory.

7.5.1 Detailed Description

Configuration class.

The class consumes the `taoJSON` library. A configuration is read from a `JAXN`-formatted file.

7.5.2 Constructor & Destructor Documentation

7.5.2.1 Configuration()

```
OFIQ_LIB::Configuration::Configuration (
    const std::string & configDir,
    const std::string & configFilename )
```

Constructor.

Parameters

<code>configDir</code>	Directory from which a JAXN configuration is read. The path can be absolute or relative to the path of the current working directory.
<code>configFilename</code>	Name of the JAXN configuration file in <code>configDir</code> .

7.5.3 Member Function Documentation

7.5.3.1 GetBool() [1/2]

```
bool OFIQ_LIB::Configuration::GetBool (
    const std::string & key ) const
```

Accesses a boolean configuration.

Parameters

<code>key</code>	Key of the configuration.
------------------	---------------------------

Returns

The accessed boolean configuration.

Exceptions

<code>OFIQ_LIB::OFIQError</code>	if the configuration was not successfully accessed.
----------------------------------	---

7.5.3.2 **GetBool()** [2/2]

```
bool OFIQ_LIB::Configuration::GetBool (
    const std::string & key,
    bool & value ) const
```

Accesses a boolean configuration.

Parameters

<i>key</i>	Key of the configuration.
<i>value</i>	Boolean reference to where the configuration result is stored.

Returns

`true` if the configuration was successfully accessed; otherwise, if the configuration was not successfully accessed, the function returns `false`.

7.5.3.3 **getDataDir()**

```
std::string OFIQ_LIB::Configuration::getDataDir ( ) const
```

Access configuration directory.

The configuration directory has been specified in the constructor or afterwards by the [SetDataDir\(\)](#) method.

Returns

String representation of the configuration directory.

7.5.3.4 **GetNumber()** [1/2]

```
double OFIQ_LIB::Configuration::GetNumber (
    const std::string & key ) const
```

Accesses a double configuration.

Parameters

<i>key</i>	Key of the configuration.
------------	---------------------------

Returns

The accessed double configuration.

Exceptions

<i>OFIQ_LIB::OFIQError</i>	if the configuration was not successfully accessed.
----------------------------	---

7.5.3.5 GetNumber() [2/2]

```
bool OFIQ_LIB::Configuration::GetNumber (
    const std::string & key,
    double & value ) const
```

Accesses a double configuration.

Parameters

<i>key</i>	Key of the configuration.
<i>value</i>	Reference to a double type to where the configuration result is stored.

Returns

`true` if the configuration was successfully accessed; otherwise, if the configuration was not successfully accessed, the function returns `false`.

7.5.3.6 GetString() [1/2]

```
std::string OFIQ_LIB::Configuration::GetString (
    const std::string & key ) const
```

Accesses a string configuration.

Parameters

<i>key</i>	Key of the configuration.
------------	---------------------------

Returns

The accessed string configuration.

Exceptions

<i>OFIQ_LIB::OFIQError</i>	if the configuration was not successfully accessed.
----------------------------	---

7.5.3.7 GetString() [2/2]

```
bool OFIQ_LIB::Configuration::GetString (
    const std::string & key,
    std::string & value ) const
```

Accesses a string configuration.

Parameters

<i>key</i>	Key of the configuration.
<i>value</i>	std::string reference to where the configuration result is stored.

Returns

true if the configuration was successfully accessed; otherwise, if the configuration was not successfully accessed, the function returns false.

7.5.3.8 GetStringList()

```
bool OFIQ_LIB::Configuration::GetStringList (
    const std::string & key,
    std::vector< std::string > & value ) const
```

Accesses an array of strings configured.

The string list will not be emptied; any strings read will be appended.

Parameters

<i>key</i>	Key of the configuration.
<i>value</i>	Reference to a string list to where the configuration result is stored.

Returns

true if the configuration was successfully accessed; otherwise, if the configuration was not successfully accessed, the function returns false.

7.5.3.9 SetDataDir()

```
void OFIQ_LIB::Configuration::SetDataDir (
    std::string dataDir )
```

Sets the configuration directory.

Parameters

<i>dataDir</i>	String representation of the configuration directory.
----------------	---

Attention

The configurations will not be updated when this method is called; it causes only an update of an internal private path member.

7.5.4 Member Data Documentation**7.5.4.1 m_dataDir**

```
std::filesystem::path OFIQ_LIB::Configuration::m_dataDir [private]
```

Path to the configuration directory.

The member is set either by the constructor or by the [SetDataDir\(\)](#) method.

7.5.4.2 parameters

```
std::map<std::string, tao::json::value, std::less<> > OFIQ_LIB::Configuration::parameters [private]
```

Map holding all configuration that can be accessed using a string key.

The documentation for this class was generated from the following file:


- [Configuration.h](#)

7.6 OFIQ_LIB::modules::measures::CropOfTheFaceImage Class Reference

Implementation of the crop of the face image measure.

```
#include <CropOfTheFaceImage.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::CropOfTheFaceImage:

**Public Member Functions**

- [CropOfTheFaceImage](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Implementation of the crop of the face image measure.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.6.1 Detailed Description

Implementation of the crop of the face image measure.

The crop of the face images measures whether the face is centered on the input image by comparing the resolution of the image with the landmarks detected during the pre-processing.

7.6.2 Constructor & Destructor Documentation

7.6.2.1 CropOfTheFaceImage()

```
OFIQ_LIB::modules::measures::CropOfTheFaceImage::CropOfTheFaceImage (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.6.3 Member Function Documentation

7.6.3.1 Execute()

```
void OFIQ_LIB::modules::measures::CropOfTheFaceImage::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Implementation of the crop of the face image measure.

The crop of the face images measures whether the face is centered on the input image by comparing the resolution of the image with the landmarks detected during the pre-processing.

Parameters

<i>session</i>	Session object.
----------------	-----------------

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [CropOfTheFacelImage.h](#)

7.7 OFIQ_LIB::modules::measures::DynamicRange Class Reference

Implementation of the dynamic range measure.

```
#include <DynamicRange.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::DynamicRange:



Public Member Functions

- [DynamicRange](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses dynamic range.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.7.1 Detailed Description

Implementation of the dynamic range measure.

The dynamic range is computed from the luminance histogram. of the facial image.

7.7.2 Constructor & Destructor Documentation

7.7.2.1 DynamicRange()

```
OFIQ_LIB::modules::measures::DynamicRange::DynamicRange (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which the measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.7.3 Member Function Documentation

7.7.3.1 Execute()

```
void OFIQ_LIB::modules::measures::DynamicRange::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses dynamic range.

Assessment of the dynamic range is computed from the luminance histogram.

Parameters

<i>session</i>	Session object.
----------------	-----------------

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:

- [DynamicRange.h](#)

7.8 OFIQ_LIB::modules::measures::Executor Class Reference

This class takes care of the computation of the measures activated.

```
#include <Executor.h>
```

Public Member Functions

- [Executor](#) (std::vector< std::unique_ptr< [Measure](#) > > [measures](#))
Construct a new Executor object.
- void [ExecuteAll](#) ([Session](#) &i_currentSession) const
Run the computation of the activated measures on the data of the provided session.
- const std::vector< std::unique_ptr< [Measure](#) > > & [GetMeasures](#) () const
Return the list of the activated measures.

Private Attributes

- std::vector< std::unique_ptr< [Measure](#) > > [measures](#)
Container for access to the measures to be computed.

7.8.1 Detailed Description

This class takes care of the computation of the measures activated.

7.8.2 Constructor & Destructor Documentation

7.8.2.1 Executor()

```
OFIQ_LIB::modules::measures::Executor::Executor (
    std::vector< std::unique_ptr< Measure > > measures ) [inline], [explicit]
```

Construct a new Executor object.

Parameters

<i>measures</i>	Provide access to the activated measures.
-----------------	---

7.8.3 Member Function Documentation

7.8.3.1 ExecuteAll()

```
void OFIQ_LIB::modules::measures::Executor::ExecuteAll (
    Session & i_currentSession ) const
```

Run the computation of the activated measures on the data of the provided session.

Parameters

<i>i_currentSession</i>	Container providing the data required for the computation of the measures.
-------------------------	--

7.8.3.2 GetMeasures()

```
const std::vector< std::unique_ptr< Measure > > & OFIQ_LIB::modules::measures::Executor::↔
GetMeasures ( ) const [inline]
```

Return the list of the activated measures.

7.8.4 Member Data Documentation

7.8.4.1 measures

```
std::vector<std::unique_ptr<Measure> > OFIQ_LIB::modules::measures::Executor::measures [private]
```

Container for access to the measures to be computed.

The documentation for this class was generated from the following file:


- [Executor.h](#)

7.9 OFIQ_LIB::modules::measures::ExpressionNeutrality Class Reference

Provides a class implementing the expression neutrality measure.

```
#include <ExpressionNeutrality.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::ExpressionNeutrality:



Public Member Functions

- [ExpressionNeutrality](#) (const [Configuration](#) &configuration, [Session](#) &session)
Construct a new Expression Neutrality object.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run the computation based on the data passed by the session object.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Attributes

- [ONNXRuntimeSegmentation m_onnxRuntimeEnvCNN1](#)
Instance of the enet_b0_8_best_vgaf_embed2 model. Set by ExpressionNeutrality.cnn1_model_path in the configuration file.
- [ONNXRuntimeSegmentation m_onnxRuntimeEnvCNN2](#)
Instance of the enet_b2_8 model. Set by ExpressionNeutrality.cnn2_model_path in the configuration file.
- std::shared_ptr< cv::ml::Boost > [classifier](#)
Instance of the AdaBoost classifier Set by ExpressionNeutrality.adaboost_model_path in the configuration file.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.9.1 Detailed Description

Provides a class implementing the expression neutrality measure.

The algorithm uses the CNN models enet_b0_8_best_vgaf and enet_b2_8 from <https://github.com/HSE-asavchenko/face-emotion-recognition> as feature extractors and an AdaBoost classifier implemented in OpenCV. Inspired by Grimmer et al. [9], both CNN models have been modified to also output the embeddings of the second last layer, and have been converted to ONNX.

7.9.2 Constructor & Destructor Documentation

7.9.2.1 ExpressionNeutrality()

```
OFIQ_LIB::modules::measures::ExpressionNeutrality::ExpressionNeutrality (
    const Configuration & configuration,
    Session & session )
```

Construct a new Expression Neutrality object.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.9.3 Member Function Documentation

7.9.3.1 Execute()

```
void OFIQ_LIB::modules::measures::ExpressionNeutrality::Execute (  
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Run the computation based on the data passed by the session object.

Parameters

<i>session</i>	Session object
----------------	----------------

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.9.4 Member Data Documentation

7.9.4.1 classifier

```
std::shared_ptr<cv::ml::Boost> OFIQ_LIB::modules::measures::ExpressionNeutrality::classifier  
[private]
```

Instance of the AdaBoost classifier Set by ExpressionNeutrality.adaboost_model_path in the configuration file.

7.9.4.2 m_onnxRuntimeEnvCNN1

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::measures::ExpressionNeutrality::m_onnxRuntimeEnv↔  
CNN1 [private]
```

Instance of the enet_b0_8_best_vgaf_embed2 model. Set by ExpressionNeutrality.cnn1_model_path in the configuration file.

7.9.4.3 m_onnxRuntimeEnvCNN2

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::measures::ExpressionNeutrality::m_onnxRuntimeEnv↔  
CNN2 [private]
```

Instance of the enet_b2_8 model. Set by ExpressionNeutrality.cnn2_model_path in the configuration file.

The documentation for this class was generated from the following file:


- [ExpressionNeutrality.h](#)

7.10 OFIQ_LIB::modules::measures::EyesOpen Class Reference

Implementation of the eyes open measure.

```
#include <EyesOpen.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::EyesOpen:



Public Member Functions

- [EyesOpen](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses eyes openness.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.10.1 Detailed Description

Implementation of the eyes open measure.

Eyes openness is based on computing eyes aspect ratios of both eyes from eye landmarks.

7.10.2 Constructor & Destructor Documentation

7.10.2.1 EyesOpen()

```
OFIQ_LIB::modules::measures::EyesOpen::EyesOpen (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.10.3 Member Function Documentation

7.10.3.1 Execute()

```
void OFIQ_LIB::modules::measures::EyesOpen::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Assesses eyes openness.

Eyes openness is based on computing eyes aspect ratios of both eyes from eye landmarks.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

See also

[Session::getAlignedFaceLandmarks\(\)](#)

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [EyesOpen.h](#)

7.11 OFIQ_LIB::modules::measures::EyesVisible Class Reference

Implementation of the eyes visible measure.

```
#include <EyesVisible.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::EyesVisible:



Public Member Functions

- [EyesVisible](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses eyes visibility.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- void [AddSigmoid](#) (OFIQ::QualityMeasure measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) (OFIQ::QualityMeasure measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.11.1 Detailed Description

Implementation of the eyes visible measure.

Eyes visibility is assessed by measuring the coverage of the eye visibility zone with the result of face occlusion segmentation computed during pre-processing.

7.11.2 Constructor & Destructor Documentation

7.11.2.1 EyesVisible()

```
OFIQ_LIB::modules::measures::EyesVisible::EyesVisible (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.11.3 Member Function Documentation

7.11.3.1 Execute()

```
void OFIQ_LIB::modules::measures::EyesVisible::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses eyes visibility.

Eyes visibility is assessed by measuring the coverage of the eye visibility zone with the result of face occlusion segmentation computed during pre-processing by [FaceOcclusionSegmentation](#). The pre-processing results are given by the `session` parameter.

Parameters

<code>session</code>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [EyesVisible.h](#)

7.12 OFIQ_LIB::FaceDetectorInterface Class Reference

Provides the interface class to the face detector implementations.

```
#include <detectors.h>
```

Inheritance diagram for OFIQ_LIB::FaceDetectorInterface:



Public Member Functions

- virtual [~FaceDetectorInterface](#) ()=default
Destroy the Face Detector Interface object.
- `std::vector< OFIQ::BoundingBox > detectFaces` ([OFIQ_LIB::Session](#) &session)
This function detects faces in given image.

Protected Member Functions

- virtual `std::vector< OFIQ::BoundingBox > UpdateFaces` ([OFIQ_LIB::Session](#) &session)=0
This method is to be called in derived classes to perform the detection of one/more faces on the given image.

7.12.1 Detailed Description

Provides the interface class to the face detector implementations.

This class provides the base class / interface for the integration of different implementations of a face detector.

7.12.2 Constructor & Destructor Documentation

7.12.2.1 ~FaceDetectorInterface()

```
virtual OFIQ_LIB::FaceDetectorInterface::~~FaceDetectorInterface ( ) [virtual], [default]
```

Destroy the Face Detector Interface object.

7.12.3 Member Function Documentation

7.12.3.1 detectFaces()

```
std::vector< OFIQ::BoundingBox > OFIQ_LIB::FaceDetectorInterface::detectFaces (
    OFIQ_LIB::Session & session )
```

This function detects faces in given image.

Parameters

in	<i>session</i>	Session containing relevant information for the current task.
----	----------------	---

7.12.3.2 UpdateFaces()

```
virtual std::vector< OFIQ::BoundingBox > OFIQ_LIB::FaceDetectorInterface::UpdateFaces (
    OFIQ_LIB::Session & session ) [protected], [pure virtual]
```

This method is to be called in derived classes to perform the detection of one/more faces on the given image.

Parameters

<i>session</i>	Session containing relevant information for the current task.
----------------	---

Returns

std::vector<OFIQ::BoundingBox>

Implemented in [OFIQ_LIB::modules::detectors::SSDFaceDetector](#).

The documentation for this class was generated from the following file:

- [detectors.h](#)

7.13 OFIQ::FaceImageQualityAssessment Struct Reference

Data structure storing the results of the different measurement computations.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [FaceImageQualityAssessment](#) ()=default
Default constructor.
- [FaceImageQualityAssessment](#) (const [QualityAssessments](#) &qAssessments, const [BoundingBox](#) &boundingBox)
Parameterized constructor.

Public Attributes

- [QualityAssessments](#) qAssessments
Container for storing the results of the different measure computations.
- [BoundingBox](#) boundingBox
Face region described by bounding box.

7.13.1 Detailed Description

Data structure storing the results of the different measurement computations.

7.13.2 Constructor & Destructor Documentation

7.13.2.1 FaceImageQualityAssessment() [1/2]

```
OFIQ::FaceImageQualityAssessment::FaceImageQualityAssessment ( ) [default]
```

Default constructor.

7.13.2.2 FaceImageQualityAssessment() [2/2]

```
OFIQ::FaceImageQualityAssessment::FaceImageQualityAssessment (
    const QualityAssessments & qAssessments,
    const BoundingBox & boundingBox ) [inline]
```

Parameterized constructor.

Parameters

in	<i>qAssessments</i>	
in	<i>boundingBox</i>	

7.13.3 Member Data Documentation

7.13.3.1 boundingBox

[BoundingBox](#) OFIQ::FaceImageQualityAssessment::boundingBox

Face region described by bounding box.

7.13.3.2 qAssessments

[QualityAssessments](#) OFIQ::FaceImageQualityAssessment::qAssessments

Container for storing the results of the different measure computations.

The documentation for this struct was generated from the following file:


- [ofiq_structs.h](#)

7.14 OFIQ_LIB::FaceLandmarkExtractorInterface Class Reference

Implements the base class for the face landmark extractors.

```
#include <landmarks.h>
```

Inheritance diagram for OFIQ_LIB::FaceLandmarkExtractorInterface:



Public Member Functions

- virtual [~FaceLandmarkExtractorInterface](#) ()=default
Destructor.
- [OFIQ::FaceLandmarks extractLandmarks](#) (OFIQ_LIB::Session &session)
Public method to extract landmarks from the image passed in the session object.

Protected Member Functions

- virtual [OFIQ::FaceLandmarks updateLandmarks](#) (OFIQ_LIB::Session &session)=0
Internal implementation of the derived class for extracting landmarks.

7.14.1 Detailed Description

Implements the base class for the face landmark extractors.

7.14.2 Constructor & Destructor Documentation

7.14.2.1 ~FaceLandmarkExtractorInterface()

```
virtual OFIQ_LIB::FaceLandmarkExtractorInterface::~~FaceLandmarkExtractorInterface ( ) [virtual],
[default]
```

Destructor.

7.14.3 Member Function Documentation

7.14.3.1 extractLandmarks()

```
OFIQ::FaceLandmarks OFIQ_LIB::FaceLandmarkExtractorInterface::extractLandmarks (
    OFIQ_LIB::Session & session )
```

Public method to extract landmarks from the image passed in the session object.

Parameters

<i>session</i>	Data container, including the original image and preprocessed data.
----------------	---

Returns

OFIQ::FaceLandmarks

7.14.3.2 updateLandmarks()

```
virtual OFIQ::FaceLandmarks OFIQ_LIB::FaceLandmarkExtractorInterface::updateLandmarks (
    OFIQ_LIB::Session & session ) [protected], [pure virtual]
```

Internal implementation of the derived class for extracting landmarks.

Parameters

<i>session</i>	Data container, including the original image and preprocessed data.
----------------	---

Returns

OFIQ::FaceLandmarks

Implemented in [OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor](#).

The documentation for this class was generated from the following file:

- [landmarks.h](#)

7.15 OFIQ::FaceLandmarks Struct Reference

Data structure for storing facial landmarks.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [FaceLandmarks](#) ()=default

Public Attributes

- [LandmarkType](#) type { [LandmarkType::NotSet](#) }
- [Landmarks](#) landmarks

7.15.1 Detailed Description

Data structure for storing facial landmarks.

7.15.2 Constructor & Destructor Documentation

7.15.2.1 FaceLandmarks()

```
OFIQ::FaceLandmarks::FaceLandmarks ( ) [default]
```

Default constructor.

7.15.3 Member Data Documentation

7.15.3.1 landmarks

```
Landmarks OFIQ::FaceLandmarks::landmarks
```

container for all detected landmarks.

7.15.3.2 type

```
LandmarkType OFIQ::FaceLandmarks::type { LandmarkType::NotSet }
```

Enum describing the type of the landmarks.

The documentation for this struct was generated from the following file:

- [ofiq_structs.h](#)

7.16 OFIQ_LIB::modules::landmarks::FaceMeasures Class Reference

Provides static functions doing computations with landmarks.

```
#include <FaceMeasures.h>
```

Public Member Functions

- [FaceMeasures](#) ()=delete
Constructor is deleted to avoid instantiations of this class.

Static Public Member Functions

- static double [InterEyeDistance](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, double yaw)
Computes the inter-eye distance based on the specified facial landmarks and yaw angle.
- static cv::Mat [GetFaceMask](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, const int height, const int width, const float alpha=0)
Creates a binary image of specified dimension and masks all pixels inside or on the convex hull.
- static double [GetDistance](#) (const [OFIQ::LandmarkPoint](#) &a, const [OFIQ::LandmarkPoint](#) &b)
Convenience method for computing the Euclidean distance between two landmark points.
- static double [GetDistance](#) (const [LandmarkPair](#) &pair)
Convenience method computing the Euclidean distance between two landmark points.
- static [OFIQ::LandmarkPoint](#) [GetMiddle](#) (const [OFIQ::Landmarks](#) &landmarks)
Computes the center point of the specified landmarks.
- static [OFIQ::LandmarkPoint](#) [GetMiddle](#) (const [LandmarkPair](#) &pair)
Computes the point in between two landmark points.
- static [OFIQ::LandmarkPoint](#) [GetMiddle](#) (const std::vector< [LandmarkPair](#) > &pairs)
Computes the center of the specified landmark points.
- static double [GetMaxPairDistance](#) (const [OFIQ::FaceLandmarks](#) &landmarks, [landmarks::FaceParts](#) face↔Part)
Returns this maximum of face pairs from landmarks corresponding to the specified face part.

7.16.1 Detailed Description

Provides static functions doing computations with landmarks.

7.16.2 Constructor & Destructor Documentation

7.16.2.1 FaceMeasures()

```
OFIQ_LIB::modules::landmarks::FaceMeasures::FaceMeasures ( ) [delete]
```

Constructor is deleted to avoid instantiations of this class.

7.16.3 Member Function Documentation

7.16.3.1 GetDistance() [1/2]

```
static double OFIQ_LIB::modules::landmarks::FaceMeasures::GetDistance (
    const LandmarkPair & pair ) [inline], [static]
```

Convenience method computing the Euclidean distance between two landmark points.

Parameters

<i>pair</i>	The two landmark points stored in the member <code>pair.Lower</code> and <code>pair.Upper</code> .
-------------	--

Returns

Euclidean distance.

7.16.3.2 GetDistance() [2/2]

```
static double OFIQ_LIB::modules::landmarks::FaceMeasures::GetDistance (
    const OFIQ::LandmarkPoint & a,
    const OFIQ::LandmarkPoint & b ) [static]
```

Convenience method for computing the Euclidean distance between two landmark points.

Parameters

<i>a</i>	First landmark point
<i>b</i>	Second landmark point

Returns

Euclidean distance between a and b.

7.16.3.3 GetFaceMask()

```
static cv::Mat OFIQ_LIB::modules::landmarks::FaceMeasures::GetFaceMask (
    const OFIQ::FaceLandmarks & faceLandmarks,
    const int height,
    const int width,
    const float alpha = 0 ) [static]
```

Creates a binary image of specified dimension and masks all pixels inside or on the convex hull.

All pixels on or inside the convex hull of the landmarks are set to 1; all other pixels are set to 0.

Parameters

<i>faceLandmarks</i>	Facial landmarks object
<i>height</i>	Height of the mask image
<i>width</i>	Width of the mask image
<i>alpha</i>	Should be 0; different values have only be used for NIST submissions.

Returns

Mask image

7.16.3.4 GetMaxPairDistance()

```
static double OFIQ_LIB::modules::landmarks::FaceMeasures::GetMaxPairDistance (
    const OFIQ::FaceLandmarks & landmarks,
    landmarks::FaceParts facePart ) [static]
```

Returns this maximum of face pairs from landmarks corresponding to the specified face part.

Face parts (such as mouth) consist of landmarks that have a mate. For example, the lower lip point may correspond to the upper lip point. For such face parts, the maximal separation (e.g., useful for detecting the mouth closeness or eyes openness) can be computed.

Parameters

<i>landmarks</i>	Facial landmarks
<i>facePart</i>	Face part

Returns

Maxim of face pairs

7.16.3.5 GetMiddle() [1/3]

```
static OFIQ::LandmarkPoint OFIQ_LIB::modules::landmarks::FaceMeasures::GetMiddle (
    const LandmarkPair & pair ) [inline], [static]
```

Computes the point in between two landmark points.

Parameters

<i>pair</i>	Pair of landmark points.
-------------	--------------------------

Returns

Point between the two landmark points.

7.16.3.6 GetMiddle() [2/3]

```
static OFIQ::LandmarkPoint OFIQ_LIB::modules::landmarks::FaceMeasures::GetMiddle (
    const OFIQ::Landmarks & landmarks ) [static]
```

Computes the center point of the specified landmarks.

Parameters

<i>landmarks</i>	Facial landmarks
------------------	------------------

Returns

Center point of the landmarks.

7.16.3.7 GetMiddle() [3/3]

```
static OFIQ::LandmarkPoint OFIQ_LIB::modules::landmarks::FaceMeasures::GetMiddle (
    const std::vector< LandmarkPair > & pairs ) [inline], [static]
```

Computes the center of the specified landmark points.

This is a convenience method to compute the center if the landmarks are available as a vector of landmark pairs.

Parameters

<i>pairs</i>	List of landmark pairs.
--------------	-------------------------

Returns

Center of the landmark points.

7.16.3.8 InterEyeDistance()

```
static double OFIQ_LIB::modules::landmarks::FaceMeasures::InterEyeDistance (
    const OFIQ::FaceLandmarks & faceLandmarks,
    double yaw ) [static]
```

Computes the inter-eye distance based on the specified facial landmarks and yaw angle.

If (x_0, y_0) and (x_1, y_1) are the left and right eye centres, then the following inter-eye distance is computed.

$$\text{IED} = \|(x_0, y_0) - (x_1, y_1)\|_2 \cdot \frac{1}{\cos(\alpha)}$$

where

$$\alpha = \pi \cdot \text{yaw} / 180$$

is the secant of the yaw angle.

Parameters

<i>faceLandmarks</i>	Facial landmarks
<i>yaw</i>	Yaw angle in degree

Returns

The inter-eye distance

The documentation for this class was generated from the following file:


- [FaceMeasures.h](#)

7.17 OFIQ_LIB::modules::measures::FaceOcclusionPrevention Class Reference

Implementation of the face occlusion prevention measure.

```
#include <FaceOcclusionPrevention.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::FaceOcclusionPrevention:



Public Member Functions

- [FaceOcclusionPrevention](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses absence of face occlusion.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.17.1 Detailed Description

Implementation of the face occlusion prevention measure.

Absence of face occlusion is assessed by measuring the coverage of the marked region with the result of face occlusion segmentation computed during pre-processing.

7.17.2 Constructor & Destructor Documentation

7.17.2.1 FaceOcclusionPrevention()

```
OFIQ_LIB::modules::measures::FaceOcclusionPrevention::FaceOcclusionPrevention (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.17.3 Member Function Documentation

7.17.3.1 Execute()

```
void OFIQ_LIB::modules::measures::FaceOcclusionPrevention::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Assesses absence of face occlusion.

Absence of face occlusion is assessed by measuring the coverage of the marked region with the result of face occlusion segmentation computed during pre-processing. Pre-processing results are passed to the method with the `session` parameter.

Parameters

<code>session</code>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------------	---

See also

[FaceOcclusionSegmentation](#)

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [FaceOcclusionPrevention.h](#)

7.18 OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation Class Reference

Class managing the separation of facial parts not occluded by non-facial parts from other parts.

```
#include <FaceOcclusionSegmentation.h>
```

Inheritance diagram for OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation:



Public Member Functions

- [FaceOcclusionSegmentation](#) (const [Configuration](#) &config)
Constructor.
- [~FaceOcclusionSegmentation](#) () override=default
Destructor.

Public Member Functions inherited from [OFIQ_LIB::SegmentationExtractorInterface](#)

- virtual [~SegmentationExtractorInterface](#) ()=default
Standard destructor.
- [OFIQ::Image](#) & [GetMask](#) ([OFIQ_LIB::Session](#) &session, [modules::segmentations::SegmentClassLabels](#) faceSegment)
Get a mask of the face region requested.

Protected Member Functions

- [OFIQ::Image](#) [UpdateMask](#) ([OFIQ_LIB::Session](#) &session, [modules::segmentations::SegmentClassLabels](#) faceSegment) override
Implements face occlusion segmentation.

Protected Member Functions inherited from OFIQ_LIB::SegmentationExtractorInterface

- `std::string GetLastSessionId () const`
Accesses the last session id for this interface.

Private Member Functions

- `cv::Mat GetFaceOcclusionSegmentation (const cv::Mat &alignedImage)`
Does the actual CNN-based occlusion-aware segmentation.

Private Attributes

- `ONNXRuntimeSegmentation m_onnxRuntimeEnv`
Manages CNN computations.
- `std::shared_ptr< cv::Mat > segmentationImage`
Stores the last result computed with `UpdateMask()`.
- `const std::string modelConfigItem = "params.measures.FaceOcclusionSegmentation.model_path"`
JSON/JAXN key to access path to FaceExtraction's model file from `Configuration` object.
- `const int cropLeft = 96`
Cropping parameter.
- `const int cropRight = 96`
Cropping parameter.
- `const int cropTop = 96`
Cropping parameter.
- `const int cropBottom = 96`
Cropping parameter.
- `const int scaledWidth = 224`
After cropping the aligned image, the result will be scaled to a dimension of that width for being input to the CNN-based segmentation.
- `const int scaledHeight = 224`
After cropping the aligned image, the result will be scaled to a dimension of that height for being input to the CNN-based segmentation.

7.18.1 Detailed Description

Class managing the separation of facial parts not occluded by non-facial parts from other parts.

The implementation is based on a CNN from `FaceExtraction`.

7.18.2 Constructor & Destructor Documentation

7.18.2.1 FaceOcclusionSegmentation()

```
OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::FaceOcclusionSegmentation (
    const Configuration & config ) [explicit]
```

Constructor.

Parameters

<i>config</i>	Configuration object from which some segmentation-related parameters may be read.
---------------	---

See also

[Other required configurations](#)

7.18.2.2 ~FaceOcclusionSegmentation()

```
OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::~FaceOcclusionSegmentation ( )
[override], [default]
```

Destructor.

7.18.3 Member Function Documentation**7.18.3.1 GetFaceOcclusionSegmentation()**

```
cv::Mat OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::GetFaceOcclusionSegmentation
(
    const cv::Mat & alignedImage ) [private]
```

Does the actual CNN-based occlusion-aware segmentation.

Parameters

<i>alignedImage</i>	Aligned image of dimension 616 x 616 as returned by Session::getAlignedFace() .
---------------------	---

Returns

Image where a pixel belonging to non-occluded facial parts is encoded as the byte value 1 and pixels belonging to other parts are encoded by the byte value 0.

7.18.3.2 UpdateMask()

```
OFIQ::Image OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::UpdateMask (
    OFIQ_LIB::Session & session,
    modules::segmentations::SegmentClassLabels faceSegment ) [override], [protected],
[virtual]
```

Implements face occlusion segmentation.

The function is invoked by [SegmentationExtractorInterface::GetMask\(\)](#). Invokes [GetFaceOcclusionSegmentation\(\)](#) and stores its output in the private [segmentationImage](#) member.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method.
<i>faceSegment</i>	Should be the value SegmentClassLabels::face .

Returns

Face occlusion segmentation mask.

Implements [OFIQ_LIB::SegmentationExtractorInterface](#).

7.18.4 Member Data Documentation

7.18.4.1 cropBottom

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::cropBottom = 96 [private]
```

Cropping parameter.

7.18.4.2 cropLeft

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::cropLeft = 96 [private]
```

Cropping parameter.

7.18.4.3 cropRight

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::cropRight = 96 [private]
```

Cropping parameter.

7.18.4.4 cropTop

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::cropTop = 96 [private]
```

Cropping parameter.

7.18.4.5 m_onnxRuntimeEnv

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::m_onnx↔  
RuntimeEnv [private]
```

Manages CNN computations.

7.18.4.6 modelConfigItem

```
const std::string OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::modelConfigItem
= "params.measures.FaceOcclusionSegmentation.model_path" [private]
```

JSON/JAXN key to access path to FaceExtraction's model file from [Configuration](#) object.

7.18.4.7 scaledHeight

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::scaledHeight = 224
[private]
```

After cropping the aligned image, the result will be scaled to a dimension of that height for being input to the CNN-based segmentation.

7.18.4.8 scaledWidth

```
const int OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::scaledWidth = 224 [private]
```

After cropping the aligned image, the result will be scaled to a dimension of that width for being input to the CNN-based segmentation.

7.18.4.9 segmentationImage

```
std::shared_ptr<cv::Mat> OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation::segmentation↔
Image [private]
```

Stores the last result computed with [UpdateMask\(\)](#).

The documentation for this class was generated from the following file:


- [FaceOcclusionSegmentation.h](#)

7.19 OFIQ_LIB::modules::segmentations::FaceParsing Class Reference

Class managing the separation of facial parts not occluded by non-facial parts from other parts.

```
#include <FaceParsing.h>
```

Inheritance diagram for OFIQ_LIB::modules::segmentations::FaceParsing:



Public Member Functions

- [FaceParsing](#) (const [Configuration](#) &config)
Constructor.
- [~FaceParsing](#) () override=default
Destructor.

Public Member Functions inherited from [OFIQ_LIB::SegmentationExtractorInterface](#)

- virtual [~SegmentationExtractorInterface](#) ()=default
Standard destructor.
- [OFIQ::Image](#) & [GetMask](#) ([OFIQ_LIB::Session](#) &session, [modules::segmentations::SegmentClassLabels](#) faceSegment)
Get a mask of the face region requested.

Protected Member Functions

- [OFIQ::Image](#) [UpdateMask](#) ([OFIQ_LIB::Session](#) &session, [modules::segmentations::SegmentClassLabels](#) faceSegment) override
Implements face parsing.

Protected Member Functions inherited from [OFIQ_LIB::SegmentationExtractorInterface](#)

- std::string [GetLastSessionId](#) () const
Accesses the last session id for this interface.

Private Member Functions

- void [SetImage](#) ([OFIQ_LIB::Session](#) &session)

Static Private Member Functions

- static cv::Mat [CreateBlob](#) (const cv::Mat &image, int i_imageSize_one_dim)
Creates the blob being input to the face parsing CNN.
- static std::shared_ptr< cv::Mat > [CalculateClassIds](#) (const cv::Mat &resultImage, int i_imageSize_one_dim)
Applies segmentation to the blob created from the input image and returns the result.

Private Attributes

- [ONNXRuntimeSegmentation](#) m_onnxRuntimeEnv
Manages CNN computations.
- std::shared_ptr< cv::Mat > [segmentationImage](#)
Stores the last result computed with [UpdateMask\(\)](#).
- const std::string [modelConfigItem](#) = "params.measures.FaceParsing.model_path"
JSON/JAXN key to access path to [BiSeNet](#) model in ONNX format from [Configuration](#) object.
- const int [imageSize](#) = 400
Face parsing target dimension.
- const int [cropLeft](#) = 30
Cropping parameter.
- const int [cropRight](#) = 30
Cropping parameter.
- const int [cropTop](#) = 0
Cropping parameter.
- const int [cropBottom](#) = 60
Cropping parameter.

7.19.1 Detailed Description

Class managing the separation of facial parts not occluded by non-facial parts from other parts.

Implements a [BiSeNet](#)-based face parsing. The aligned face image is cropped and then scaled to the dimension 400 x 400. All pixels of the resulting image are assigned to one of the following class.

value	class
0	background
1	face skin
2	left eye brow
3	right eye brow
4	left eye
5	right eye
6	eyeglasses
7	left ear
8	right ear
9	earring
10	nose
11	mouth
12	upper lip
13	lower lip
14	neck
15	necklace
16	clothing
17	hair
18	head covering

The result of face parsing is an image (matrix) of dimension 400 x 400 where each pixel is assigned with one of the values listed in the table from above.

7.19.2 Constructor & Destructor Documentation

7.19.2.1 FaceParsing()

```
OFIQ_LIB::modules::segmentations::FaceParsing::FaceParsing (
    const Configuration & config ) [explicit]
```

Constructor.

Parameters

<i>config</i>	Configuration object from which related parameters may be read.
---------------	---

See also

For configuration of face parsing, see [Other required configurations](#)

7.19.2.2 ~FaceParsing()

OFIQ_LIB::modules::segmentations::FaceParsing::~~FaceParsing () [override], [default]

Destructor.

7.19.3 Member Function Documentation

7.19.3.1 CalculateClassIds()

```
static std::shared_ptr< cv::Mat > OFIQ_LIB::modules::segmentations::FaceParsing::Calculate←
ClassIds (
    const cv::Mat & resultImage,
    int i_imageSize_one_dim ) [static], [private]
```

Applies segmentation to the blob created from the input image and returns the result.

Is invoked by [SetImage\(\)](#).

Parameters

<i>resultImage</i>	Blob being created by one of the CreateBlob functions.
<i>i_imageSize_one_dim</i>	Specifies the size of the blob being input to the face parsing CNN; should be 400, such that a blob of dimension 400 x 400 is created.

Returns

Result of face parsing.

7.19.3.2 CreateBlob()

```
static cv::Mat OFIQ_LIB::modules::segmentations::FaceParsing::CreateBlob (
    const cv::Mat & image,
    int i_imageSize_one_dim ) [static], [private]
```

Creates the blob being input to the face parsing CNN.

Parameters

<i>image</i>	Input image
<i>i_imageSize_one_dim</i>	Specifies the size of the blob being input to the face parsing CNN; should be 400, such that a blob of dimension 400 x 400 is created.

Returns

Blob of requested dimension.

7.19.3.3 SetImage()

```
void OFIQ_LIB::modules::segmentations::FaceParsing::SetImage (
    OFIQ_LIB::Session & session ) [private]
```

7.19.3.4 UpdateMask()

```
OFIQ::Image OFIQ_LIB::modules::segmentations::FaceParsing::UpdateMask (
    OFIQ_LIB::Session & session,
    modules::segmentations::SegmentClassLabels faceSegment ) [override], [protected],
[virtual]
```

Implements face parsing.

The function is invoked by [SegmentationExtractorInterface::GetMask\(\)](#). It crops the aligned face image returned by [Session::getAlignedFace\(\)](#) as configured by private member variables. The result is scaled to the dimension of 400 x 400 and passed to the [BiSeNet](#) CNN. The output is returned as face parsing.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method.
<i>faceSegment</i>	Enum value encoding the requested face segment. If the value is SegmentClassLabels::face then an image of dimension 400 x 400 is returned assigning each pixel a value between 0 and 18 as in the table of FaceParsing ; otherwise a binary mask of dimension 400 x 400 is returned with the requested face segment and morphologically extended (kernel size 3) is returned.

Returns

Face parsing image of dimension 400 x 400 where each pixel is assigned with one of the values described in the table of the [OFIQ_LIB::modules::segmentations::FaceParsing](#) class documentation.

Implements [OFIQ_LIB::SegmentationExtractorInterface](#).

7.19.4 Member Data Documentation

7.19.4.1 cropBottom

```
const int OFIQ_LIB::modules::segmentations::FaceParsing::cropBottom = 60 [private]
```

Cropping parameter.

7.19.4.2 cropLeft

```
const int OFIQ_LIB::modules::segmentations::FaceParsing::cropLeft = 30 [private]
```

Cropping parameter.

7.19.4.3 cropRight

```
const int OFIQ_LIB::modules::segmentations::FaceParsing::cropRight = 30 [private]
```

Cropping parameter.

7.19.4.4 cropTop

```
const int OFIQ_LIB::modules::segmentations::FaceParsing::cropTop = 0 [private]
```

Cropping parameter.

7.19.4.5 imageSize

```
const int OFIQ_LIB::modules::segmentations::FaceParsing::imageSize = 400 [private]
```

Face parsing target dimension.

7.19.4.6 m_onnxRuntimeEnv

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::segmentations::FaceParsing::m_onnxRuntimeEnv [private]
```

Manages CNN computations.

7.19.4.7 modelConfigItem

```
const std::string OFIQ_LIB::modules::segmentations::FaceParsing::modelConfigItem = "params.↔  
measures.FaceParsing.model_path" [private]
```

JSON/JAXN key to access path to [BiSeNet](#) model in ONNX format from [Configuration](#) object.

7.19.4.8 segmentationImage

```
std::shared_ptr<cv::Mat> OFIQ_LIB::modules::segmentations::FaceParsing::segmentationImage  
[private]
```

Stores the last result computed with [UpdateMask\(\)](#).

The documentation for this class was generated from the following file:


- [FaceParsing.h](#)

7.20 OFIQ_LIB::modules::measures::HeadPose Class Reference

Implementation of head pose measures.

```
#include <HeadPose.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::HeadPose:



Public Member Functions

- [HeadPose](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor for HeadPose.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses head pose measure.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.20.1 Detailed Description

Implementation of head pose measures.

Head pose measures are returned for roll, pitch and yaw face angle.

7.20.2 Constructor & Destructor Documentation

7.20.2.1 HeadPose()

```
OFIQ_LIB::modules::measures::HeadPose::HeadPose (
    const Configuration & configuration,
    Session & session )
```

Constructor for HeadPose.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.20.3 Member Function Documentation

7.20.3.1 Execute()

```
void OFIQ_LIB::modules::measures::HeadPose::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Assesses head pose measure.

Quality components are computed with the help of the cosine of the native quality scores (angles).

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [HeadPose.h](#)

7.21 OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2 Class Reference

Implementation of a head pose estimator.

```
#include <HeadPose3DDFAV2.h>
```

Inheritance diagram for OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2:



Public Member Functions

- [HeadPose3DDFAV2](#) (const [Configuration](#) &config)
Constructor for HeadPose3DDFAV2.
- [~HeadPose3DDFAV2](#) () override=default
Destructor.

Public Member Functions inherited from [OFIQ_LIB::PoseEstimatorInterface](#)

- virtual [~PoseEstimatorInterface](#) ()=default
Standard destructor.
- [EulerAngle](#) & [estimatePose](#) ([OFIQ_LIB::Session](#) &session)
This function estimates the three head orientation angles.

Protected Member Functions

- void [updatePose](#) ([OFIQ_LIB::Session](#) &session, [EulerAngle](#) &pose) override
Computation of the head pose.

Private Member Functions

- cv::Mat [CropImage](#) (const cv::Mat &image, const [OFIQ::BoundingBox](#) &biggestFace)
Crop face from image. Internally the passed bounding box will be transformed to a square region.

Private Attributes

- Ort::Env `m_ortenv`
ONNXRuntime environment handle.
- std::unique_ptr< Ort::Session > `m_ort_session`
ONNXRuntime session handle.
- int64_t `m_expected_image_width` = 0
Width of the CNN used for computation, read from the loaded model.
- int64_t `m_expected_image_height` = 0
Height of the CNN used for computation, read from the loaded model.
- int64_t `m_expected_image_number_of_channels` = 0
Expected number of channels of the input image, read from the loaded model.
- int64_t `m_number_of_input_elements` = 0
Number of input elements of the CNN used for computation, read from the loaded model.
- std::array< int64_t, 4 > `inputShape`
inputShape of the CNN used for computation, read from the loaded model.

Static Private Attributes

- static const std::string `paramPoseEstimatorModel`
Name of the used CNN net, passed from the configuration.

Additional Inherited Members

Public Types inherited from OFIQ_LIB::PoseEstimatorInterface

- using `EulerAngle` = std::array<double, 3>

7.21.1 Detailed Description

Implementation of a head pose estimator.

The estimator is based on a CNN from https://github.com/cleardusk/3DDFA_V2.

7.21.2 Constructor & Destructor Documentation

7.21.2.1 HeadPose3DDFAV2()

```
OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::HeadPose3DDFAV2 (
    const Configuration & config ) [explicit]
```

Constructor for HeadPose3DDFAV2.

Parameters

<code>config</code>	Configuration from where the the path to the CNN model in ONNX format to read.
---------------------	--

7.21.2.2 ~HeadPose3DDFAV2()

OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::~~HeadPose3DDFAV2 () [override], [default]

Destructor.

7.21.3 Member Function Documentation

7.21.3.1 CropImage()

```
cv::Mat OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::CropImage (
    const cv::Mat & image,
    const OFIQ::BoundingBox & biggestFace ) [private]
```

Crop face from image. Internally the passed bounding box will be transformed to a square region.

Parameters

<i>image</i>	Input image.
<i>biggestFace</i>	Input region to be cropped.

Returns

cv::Mat Cropped face region.

7.21.3.2 updatePose()

```
void OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::updatePose (
    OFIQ_LIB::Session & session,
    EulerAngle & pose ) [override], [protected], [virtual]
```

Computation of the head pose.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed.
<i>pose</i>	Estimated head pose.

Implements [OFIQ_LIB::PoseEstimatorInterface](#).

7.21.4 Member Data Documentation

7.21.4.1 inputShape

```
std::array<int64_t, 4> OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::inputShape [private]
```

inputShape of the CNN used for computation, read from the loaded model.

7.21.4.2 m_expected_image_height

```
int64_t OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_expected_image_height = 0 [private]
```

Height of the CNN used for computation, read from the loaded model.

7.21.4.3 m_expected_image_number_of_channels

```
int64_t OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_expected_image_number_of_↔  
channels = 0 [private]
```

Expected number of channels of the input image, read from the loaded model.

7.21.4.4 m_expected_image_width

```
int64_t OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_expected_image_width = 0 [private]
```

Width of the CNN used for computation, read from the loaded model.

7.21.4.5 m_number_of_input_elements

```
int64_t OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_number_of_input_elements = 0  
[private]
```

Number of input elements of the CNN used for computation, read from the loaded model.

7.21.4.6 m_ort_session

```
std::unique_ptr<Ort::Session> OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_ort_↔  
session [private]
```

ONNXRuntime session handle.

7.21.4.7 m_ortenv

```
Ort::Env OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::m_ortenv [private]
```

ONNXRuntime environment handle.

7.21.4.8 paramPoseEstimatorModel

```
const std::string OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2::paramPoseEstimatorModel  
[static], [private]
```

Name of the used CNN net, passed from the configuration.

The documentation for this class was generated from the following file:


- [HeadPose3DDFAV2.h](#)

7.22 OFIQ_LIB::modules::measures::HeadSize Class Reference

Implementation of the head size measure.

```
#include <HeadSize.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::HeadSize:



Public Member Functions

- [HeadSize](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run computation of head size measure,.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.22.1 Detailed Description

Implementation of the head size measure.

Head size measure is based on the the distance T between the midpoint between the eyes and the chin and the height of the image. Check ISO/IEC 29794-5 for more information.

7.22.2 Constructor & Destructor Documentation

7.22.2.1 HeadSize()

```
OFIQ_LIB::modules::measures::HeadSize::HeadSize (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.22.3 Member Function Documentation

7.22.3.1 Execute()

```
void OFIQ_LIB::modules::measures::HeadSize::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Run computation of head size measure,.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [HeadSize.h](#)

7.23 OFIQ_LIB::modules::measures::IlluminationUniformity Class Reference

Implementation of the illumination uniformity measure.

```
#include <IlluminationUniformity.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::IlluminationUniformity:



Public Member Functions

- [IlluminationUniformity](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses illumination uniformity.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- void [AddSigmoid](#) (OFIQ::QualityMeasure measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) (OFIQ::QualityMeasure measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.23.1 Detailed Description

Implementation of the illumination uniformity measure.

Uniformity of the illumination is measured by summing up the minima of the histograms of the left and the right side of the face.

7.23.2 Constructor & Destructor Documentation

7.23.2.1 IlluminationUniformity()

```
OFIQ_LIB::modules::measures::IlluminationUniformity::IlluminationUniformity (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.23.3 Member Function Documentation

7.23.3.1 Execute()

```
void OFIQ_LIB::modules::measures::IlluminationUniformity::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses illumination uniformity.

Uniformity of the illumination is measured by summing up the minima of the histograms of the left and the right side of the face.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:

- [IlluminationUniformity.h](#)

7.24 OFIQ::Image Struct Reference

Struct representing a single image.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [Image](#) ()=default
Constructor.
- [Image](#) (uint16_t [width](#), uint16_t [height](#), uint8_t [depth](#), std::shared_ptr< uint8_t > &[data](#))
Constructor.
- size_t [size](#) () const
This function returns the size of the image data.

Public Attributes

- uint16_t [width](#) { 0 }
- uint16_t [height](#) { 0 }
- uint8_t [depth](#) { 24 }
- std::shared_ptr< uint8_t > [data](#)

7.24.1 Detailed Description

Struct representing a single image.

7.24.2 Constructor & Destructor Documentation

7.24.2.1 Image() [1/2]

```
OFIQ::Image::Image ( ) [default]
```

Constructor.

7.24.2.2 Image() [2/2]

```
OFIQ::Image::Image (
    uint16_t width,
    uint16_t height,
    uint8_t depth,
    std::shared_ptr< uint8_t > & data ) [inline]
```

Constructor.

Parameters

<i>width</i>	of the image.
<i>height</i>	of the image.
<i>depth</i>	of the image
<i>data</i>	of the image.

7.24.3 Member Function Documentation

7.24.3.1 size()

```
size_t OFIQ::Image::size ( ) const [inline]
```

This function returns the size of the image data.

7.24.4 Member Data Documentation

7.24.4.1 data

```
std::shared_ptr<uint8_t> OFIQ::Image::data
```

Managed pointer to raster scanned data. Either RGB color or intensity. If `image_depth == 24` this points to 3WH bytes RGBRGBRGB... If `image_depth == 8` this points to WH bytes IIIIII

7.24.4.2 depth

```
uint8_t OFIQ::Image::depth { 24 }
```

Number of bits per pixel. Legal values are 8 and 24.

7.24.4.3 height

```
uint16_t OFIQ::Image::height { 0 }
```

Number of pixels vertically

7.24.4.4 width

```
uint16_t OFIQ::Image::width { 0 }
```

Number of pixels horizontally

The documentation for this struct was generated from the following file:


- [ofiq_structs.h](#)

7.25 OFIQ_LIB::modules::measures::InterEyeDistance Class Reference

Implementation of the inter-eye distance measure.

```
#include <InterEyeDistance.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::InterEyeDistance:



Public Member Functions

- [InterEyeDistance](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses inter-eye distance.

Public Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- void [AddSigmoid](#) (OFIQ::QualityMeasure measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) (OFIQ::QualityMeasure measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.25.1 Detailed Description

Implementation of the inter-eye distance measure.

Inter-eye distance assessment is based on computing the Euclidean length of both eyes' centres and multiplication with the secant of the yaw angle computed during pre-processing.

7.25.2 Constructor & Destructor Documentation

7.25.2.1 InterEyeDistance()

```
OFIQ_LIB::modules::measures::InterEyeDistance::InterEyeDistance (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.25.3 Member Function Documentation

7.25.3.1 Execute()

```
void OFIQ_LIB::modules::measures::InterEyeDistance::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses inter-eye distance.

Inter-eye distance assessment is based on computing the Euclidean length of both eyes' centres and multiplication with the secant of the yaw angle computed during pre-processing.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [InterEyeDistance.h](#)

7.26 OFIQ::Interface Class Reference

The interface to FACE QA implementation.

```
#include <ofiq_lib.h>
```

Inheritance diagram for OFIQ::Interface:



Public Member Functions

- virtual [~Interface](#) ()=default
Default Destructor.
- virtual [OFIQ::ReturnStatus initialize](#) (const std::string &configDir, const std::string &configFileName)=0
This function initializes the implementation under test. The implementation under test should set all parameters.
- virtual [OFIQ::ReturnStatus scalarQuality](#) (const [OFIQ::Image](#) &face, double &quality)=0
This function takes an image and outputs a quality scalar.
- virtual [OFIQ::ReturnStatus vectorQuality](#) (const [OFIQ::Image](#) &image, [OFIQ::FaceImageQualityAssessment](#) &assessments)=0
This function takes an image and outputs quality information.

Static Public Member Functions

- static `OFIQ_EXPORT` `std::shared_ptr< Interface > getImplementation ()`
Factory method to return a shared pointer to the Interface object.

7.26.1 Detailed Description

The interface to FACE QA implementation.

Implement this interface by sub-classing this class and implementing each method therein.

7.26.2 Constructor & Destructor Documentation

7.26.2.1 ~Interface()

```
virtual OFIQ::Interface::~~Interface ( ) [virtual], [default]
```

Default Destructor.

7.26.3 Member Function Documentation

7.26.3.1 getImplementation()

```
static OFIQ_EXPORT std::shared_ptr< Interface > OFIQ::Interface::getImplementation ( ) [static]
```

Factory method to return a shared pointer to the Interface object.

This function is implemented by the submitted library and must return a shared pointer to the Interface object.

This function MUST be implemented.

Note

A possible implementation might be: `return (std::make_shared<Implementation>());`

Returns

`std::shared_ptr<Interface>` pointer to the implementation of the interface.

7.26.3.2 initialize()

```
virtual OFIQ::ReturnStatus OFIQ::Interface::initialize (
    const std::string & configDir,
    const std::string & configFileName ) [pure virtual]
```

This function initializes the implementation under test. The implementation under test should set all parameters.

Parameters

in	<i>configDir</i>	string representation of the directory containing the configuration file specified by configFileName
in	<i>configFileName</i>	An string value encoding the JAXN configuration file name

Returns

OFIQ::ReturnStatus indicating if the initialization was successful.

Implemented in [OFIQ_LIB::OFIQImpl](#).

7.26.3.3 scalarQuality()

```
virtual OFIQ::ReturnStatus OFIQ::Interface::scalarQuality (
    const OFIQ::Image & face,
    double & quality ) [pure virtual]
```

This function takes an image and outputs a quality scalar.

Parameters

in	<i>face</i>	Single face image
out	<i>quality</i>	A scalar value assessment of image quality. The legal values are [0,100] So, a low value indicates high expected FNMR. A value of -1.0 indicates a failed attempt to calculate a quality score or the value is unassigned.

Returns

OFIQ::ReturnStatus

Implemented in [OFIQ_LIB::OFIQImpl](#).

7.26.3.4 vectorQuality()

```
virtual OFIQ::ReturnStatus OFIQ::Interface::vectorQuality (
    const OFIQ::Image & image,
    OFIQ::FaceImageQualityAssessment & assessments ) [pure virtual]
```

This function takes an image and outputs quality information.

The quality assessment should be performed on the largest detected face.

Parameters

in	<i>image</i>	Single face image
out	<i>assessments</i>	An ImageQualityAssessments structure. The implementation should populate 1) the bounding box and 2) those items in the QualityAssessments object that the developer chooses to implement 3) face landmarks

Returns

OFIQ::ReturnStatus

Implemented in [OFIQ_LIB::OFIQImpl](#).

The documentation for this class was generated from the following file:

- [ofiq_lib.h](#)

7.27 OFIQ_LIB::modules::landmarks::LandmarkPair Struct Reference

Data container for storing pairs of landmarks.

```
#include <PartExtractor.h>
```

Public Member Functions

- [LandmarkPair](#) ([OFIQ::LandmarkPoint](#) upper, [OFIQ::LandmarkPoint](#) lower)
Parameterized constructor.

Public Attributes

- [OFIQ::LandmarkPoint Upper](#)
First Landmark.
- [OFIQ::LandmarkPoint Lower](#)
second landmark

7.27.1 Detailed Description

Data container for storing pairs of landmarks.

in some computation special landmarks are bound together via the LandmarkPair struct.

7.27.2 Constructor & Destructor Documentation

7.27.2.1 LandmarkPair()

```
OFIQ_LIB::modules::landmarks::LandmarkPair::LandmarkPair (  
    OFIQ::LandmarkPoint upper,  
    OFIQ::LandmarkPoint lower ) [inline]
```

Parameterized constructor.

Parameters

in	<i>upper</i>	LandmarkPoint of first landmark.
in	<i>lower</i>	LandmarkPoint of second landmark.

7.27.3 Member Data Documentation

7.27.3.1 Lower

`OFIQ::LandmarkPoint OFIQ_LIB::modules::landmarks::LandmarkPair::Lower`

second landmark

7.27.3.2 Upper

`OFIQ::LandmarkPoint OFIQ_LIB::modules::landmarks::LandmarkPair::Upper`

First Landmark.

The documentation for this struct was generated from the following file:

- [PartExtractor.h](#)

7.28 OFIQ::LandmarkPoint Struct Reference

Data structure to describe the x and y coordinate of a landmark.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [LandmarkPoint](#) ()=default
Default constructor.
- [LandmarkPoint](#) (int16_t i_x, int16_t i_y)
Parameterized constructor.

Public Attributes

- int16_t `x` {-1}
x - coordinate
- int16_t `y` {-1}
y - coordinate

7.28.1 Detailed Description

Data structure to describe the x and y coordinate of a landmark.

7.28.2 Constructor & Destructor Documentation

7.28.2.1 LandmarkPoint() [1/2]

```
OFIQ::LandmarkPoint::LandmarkPoint ( ) [default]
```

Default constructor.

7.28.2.2 LandmarkPoint() [2/2]

```
OFIQ::LandmarkPoint::LandmarkPoint (
    int16_t i_x,
    int16_t i_y ) [inline]
```

Parameterized constructor.

Parameters

i_x _↔ <i>X</i>	x - coordinate of the landmark.
i_y _↔ <i>y</i>	y - coordinate of the landmark.

7.28.3 Member Data Documentation

7.28.3.1 x

```
int16_t OFIQ::LandmarkPoint::x { -1 }
```

x - coordinate

7.28.3.2 y

```
int16_t OFIQ::LandmarkPoint::y { -1 }
```

y - coordinate

The documentation for this struct was generated from the following file:


- [ofiq_structs.h](#)

7.29 OFIQ_LIB::modules::measures::Luminance Class Reference

Implementation of two luminance measures.

```
#include <Luminance.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::Luminance:



Public Member Functions

- [Luminance](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses luminance mean and luminance variance measures.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & *configuration*
Reference to the configuration with which the measure constructor has been invoked.

7.29.1 Detailed Description

Implementation of two luminance measures.

On execution, two measures will be assessed: Luminance mean and luminance variance.

7.29.2 Constructor & Destructor Documentation

7.29.2.1 Luminance()

```
OFIQ_LIB::modules::measures::Luminance::Luminance (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.29.3 Member Function Documentation

7.29.3.1 Execute()

```
void OFIQ_LIB::modules::measures::Luminance::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Assesses luminance mean and luminance variance measures.

On execution, two measures will be assessed: Luminance mean and luminance variance.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [Luminance.h](#)

7.30 OFIQ_LIB::modules::measures::Measure Class Reference

Base class for measures implemented in OFIQ.

```
#include <Measure.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::Measure:



Public Member Functions

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual void [Execute](#) ([OFIQ_LIB::Session](#) &session)=0
Abstract quality assessment function.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const

- Returns the name of the measure.*
- virtual [OFIQ::QualityMeasure GetQualityMeasure](#) () const

Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)

Inserts the result of a quality assessment in the session object.

Protected Member Functions

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)

Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)

Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)

Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)

Maps a native quality score to a quality component value.

Static Protected Member Functions

- static double [Sigmoid](#) (double x, double x0, double w)

Sigmoid function.

Protected Attributes

- const [Configuration](#) & configuration

Reference to the configuration with which the measure constructor has been invoked.

Static Private Member Functions

- static double [ScalarConversion](#) (double rawValue, const [SigmoidParameters](#) &par)

Applies a sigmoid-based quality mapping to a native quality score and outputs the result.
- static std::string [GetMeasureName](#) ([OFIQ::QualityMeasure](#) measure)

Returns the name of the specified measure.
- static std::string [ExpandKey](#) (std::string_view rawKey)

Expands the raw key of a measure to the key accessing its Sigmoid-based quality mapping.

Private Attributes

- std::map< std::string, [SigmoidParameters](#), std::less<> > sigmoidMap

Used to map the measure name to the sigmoid-based quality mapping function.
- [OFIQ::QualityMeasure m_measure](#) = [OFIQ::QualityMeasure::NotSet](#)

Value encoding the measure type.

7.30.1 Detailed Description

Base class for measures implemented in OFIQ.

7.30.2 Constructor & Destructor Documentation

7.30.2.1 Measure()

```
OFIQ_LIB::modules::measures::Measure::Measure (
    const Configuration & configuration,
    const OFIQ_LIB::Session & ,
    OFIQ::QualityMeasure measure ) [inline]
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
<i>measure</i>	Enum of the measure.

7.30.2.2 ~Measure()

```
virtual OFIQ_LIB::modules::measures::Measure::~~Measure ( ) [virtual], [default]
```

Destructor.

7.30.3 Member Function Documentation

7.30.3.1 AddSigmoid() [1/2]

```
void OFIQ_LIB::modules::measures::Measure::AddSigmoid (
    const std::string & key,
    SigmoidParameters defaultValues ) [protected]
```

Reads sigmoid-function based quality mapping from the configuration.

The parameters are read from the configuration reference member [OFIQ_LIB::modules::measures::Measure::configuration](#). If a parameter is not configured, its default value is chosen from the `defaultValues` argument.

Parameters

<i>key</i>	Key/name of the measure of which mapping is configured.
<i>defaultValues</i>	Parameters from which default values of non-configured parameters are chosen.

7.30.3.2 AddSigmoid() [2/2]

```
void OFIQ_LIB::modules::measures::Measure::AddSigmoid (
    OFIQ::QualityMeasure measure,
    const SigmoidParameters & defaultValues ) [protected]
```

Reads sigmoid-function based quality mapping from the configuration.

The parameters are read from the configuration reference member [OFIQ_LIB::modules::measures::Measure::configuration](#). If a parameter is not configured, its default value is chosen from the `defaultValues` argument.

Parameters

<i>measure</i>	Enum value encoding the measure for which the mapping is configured.
<i>defaultValues</i>	Parameters from which default values of non-configured parameters are chosen.

7.30.3.3 Execute()

```
virtual void OFIQ_LIB::modules::measures::Measure::Execute (
    OFIQ_LIB::Session & session ) [pure virtual]
```

Abstract quality assessment function.

After quality assessment of the implemented measure, the method should invoke [SetQualityMeasure\(\)](#) to insert the result of quality assessment in `session`.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implemented in [OFIQ_LIB::modules::measures::BackgroundUniformity](#), [OFIQ_LIB::modules::measures::CompressionArtifacts](#), [OFIQ_LIB::modules::measures::CropOfTheFacelImage](#), [OFIQ_LIB::modules::measures::DynamicRange](#), [OFIQ_LIB::modules::measures::EyesOpen](#), [OFIQ_LIB::modules::measures::EyesVisible](#), [OFIQ_LIB::modules::measures::FaceOcclusion](#), [OFIQ_LIB::modules::measures::HeadPose](#), [OFIQ_LIB::modules::measures::HeadSize](#), [OFIQ_LIB::modules::measures::Illumination](#), [OFIQ_LIB::modules::measures::InterEyeDistance](#), [OFIQ_LIB::modules::measures::Luminance](#), [OFIQ_LIB::modules::measures::MouthOcclusionPrevention](#), [OFIQ_LIB::modules::measures::NaturalColour](#), [OFIQ_LIB::modules::measures::NoHeadCoverings](#), [OFIQ_LIB::modules::measures::OverExposurePrevention](#), [OFIQ_LIB::modules::measures::Sharpness](#), [OFIQ_LIB::modules::measures::SingleFacePresent](#), [OFIQ_LIB::modules::measures::UnifiedQualityScore](#) and [OFIQ_LIB::modules::measures::UnifiedQualityScore](#).

7.30.3.4 ExecuteScalarConversion() [1/2]

```
double OFIQ_LIB::modules::measures::Measure::ExecuteScalarConversion (
    const std::string & key,
    double rawValue ) [protected]
```

Maps a native quality score to a quality component value.

Parameters

<i>key</i>	Key/name of the measure used to read parameters from a private map member.
<i>rawValue</i>	Native quality score.

Returns

Quality component value.

7.30.3.5 ExecuteScalarConversion() [2/2]

```
double OFIQ_LIB::modules::measures::Measure::ExecuteScalarConversion (
    OFIQ::QualityMeasure measure,
    double rawValue ) [protected]
```

Maps a native quality score to a quality component value.

Parameters

<i>measure</i>	Enum value of the measure used to read parameters from a private map member.
<i>rawValue</i>	Native quality score.

Returns

Quality component value.

7.30.3.6 ExpandKey()

```
static std::string OFIQ_LIB::modules::measures::Measure::ExpandKey (
    std::string_view rawKey ) [static], [private]
```

Expands the raw key of a measure to the key accessing its Sigmoid-based quality mapping.

Parameters

<i>rawKey</i>	representation of the measure (e.g., "BackgroundUniformity").
---------------	---

Returns

std::string representation of the key accessing the quality mapping function configuration (e.g., "params.↔measures.BackgroundUniformity.Sigmoid").

7.30.3.7 GetMeasureName()

```
static std::string OFIQ_LIB::modules::measures::Measure::GetMeasureName (
    OFIQ::QualityMeasure measure ) [static], [private]
```

Returns the name of the specified measure.

Parameters

<i>measure</i>	Enum value of a measure.
----------------	--------------------------

Returns

std::string representation of the requested measure.

7.30.3.8 GetName()

```
virtual std::string OFIQ_LIB::modules::measures::Measure::GetName ( ) const [virtual]
```

Returns the name of the measure.

Unless overwritten, the member `m_measure` is passed to the private `GetMeasureName()` method and the result is returned.

Returns

std::string representation of the measures.

7.30.3.9 GetQualityMeasure()

```
virtual OFIQ::QualityMeasure OFIQ_LIB::modules::measures::Measure::GetQualityMeasure ( ) const [virtual]
```

Returns an enum encoding the measure.

Returns

Enum encoding the measure.

7.30.3.10 ScalarConversion()

```
static double OFIQ_LIB::modules::measures::Measure::ScalarConversion (
    double rawValue,
    const SigmoidParameters & par ) [inline], [static], [private]
```

Applies a sigmoid-based quality mapping to a native quality score and outputs the result.

Before output, the result is checked if it is below 0 or above

1. If it is below 0, then 0 is returned. If it is above 100, then 100 is returned.

Parameters

<i>rawValue</i>	Native quality score.
<i>par</i>	Parameters of the sigmoid-based quality mapping.

Returns

The mapped quality value.

7.30.3.11 SetQualityMeasure()

```
void OFIQ_LIB::modules::measures::Measure::SetQualityMeasure (
    OFIQ_LIB::Session & session,
    OFIQ::QualityMeasure measure,
    double rawValue,
    OFIQ::QualityMeasureReturnCode code )
```

Inserts the result of a quality assessment in the session object.

The method [ExecuteScalarConversion\(\)](#) is invoked to map the native quality score to its quality component value.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method.
<i>measure</i>	Enum value specifying this measure.
<i>rawValue</i>	Native quality score
<i>code</i>	Value indicating whether the quality assessment was computed successfully or otherwise (e.g., failureToAssess).

7.30.3.12 Sigmoid()

```
static double OFIQ_LIB::modules::measures::Measure::Sigmoid (
    double x,
    double x0,
    double w ) [inline], [static], [protected]
```

Sigmoid function.

Parameters

<i>x</i>	Native quality score
<i>x0</i>	Non-zero center point
<i>w</i>	Divisor

Returns

$$(1 + \exp((x0 - x)/w))^{-1}.$$

7.30.4 Member Data Documentation

7.30.4.1 configuration

```
const Configuration& OFIQ_LIB::modules::measures::Measure::configuration [protected]
```

Reference to the configuration with which the measure constructor has been invoked.

7.30.4.2 m_measure

```
OFIQ::QualityMeasure OFIQ_LIB::modules::measures::Measure::m_measure = OFIQ::QualityMeasure::NotSet
[private]
```

Value encoding the measure type.

The value is set to QualityMeasure::NotSet by default which effectively corresponds to a non-specified measure.

7.30.4.3 sigmoidMap

```
std::map<std::string, SigmoidParameters, std::less<> > OFIQ_LIB::modules::measures::Measure←
::sigmoidMap [private]
```

Used to map the measure name to the sigmoid-based quality mapping function.

The documentation for this class was generated from the following file:

- [Measure.h](#)

7.31 OFIQ_LIB::modules::measures::MeasureFactory Class Reference

Measure factor class.

```
#include <MeasureFactory.h>
```

Public Member Functions

- [MeasureFactory](#) ()=delete

Static Public Member Functions

- static std::unique_ptr< [Measure](#) > [CreateMeasure](#) (const [OFIQ::QualityMeasure](#) measure, const [Configuration](#) &configuration, [OFIQ_LIB::Session](#) &session)
Requests the creation of a measure implementation.

7.31.1 Detailed Description

Measure factor class.

7.31.2 Constructor & Destructor Documentation

7.31.2.1 MeasureFactory()

```
OFIQ_LIB::modules::measures::MeasureFactory::MeasureFactory ( ) [delete]
```

7.31.3 Member Function Documentation

7.31.3.1 CreateMeasure()

```
static std::unique_ptr< Measure > OFIQ_LIB::modules::measures::MeasureFactory::CreateMeasure (
    const OFIQ::QualityMeasure measure,
    const Configuration & configuration,
    OFIQ\_LIB::Session & session ) [static]
```

Requests the creation of a measure implementation.

Parameters

<i>measure</i>	Enum value encoding the requested measure.
<i>configuration</i>	Configuration from which measure parameters are read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method.

Attention

The function returns `nullptr` if the request of a measure is not implemented by the function.
 If any constructor of a requested measures throws something, the throw is forwarded to this function.

The documentation for this class was generated from the following file:


- [MeasureFactory.h](#)

7.32 OFIQ_LIB::modules::measures::MouthClosed Class Reference

Implementation of the mouth closed measure.

```
#include <MouthClosed.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::MouthClosed:



Public Member Functions

- [MouthClosed](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses mouth closeness.

Public Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.32.1 Detailed Description

Implementation of the mouth closed measure.

Mouth closed assessment based on computing a ratio from mouth landmarks.

7.32.2 Constructor & Destructor Documentation

7.32.2.1 MouthClosed()

```
OFIQ_LIB::modules::measures::MouthClosed::MouthClosed (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.32.3 Member Function Documentation

7.32.3.1 Execute()

```
void OFIQ_LIB::modules::measures::MouthClosed::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses mouth closeness.

Mouth closed assessment based on computing a ratio from mouth landmarks.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

See also

[Session::getAlignedFaceLandmarks\(\)](#)

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [MouthClosed.h](#)

7.33 OFIQ_LIB::modules::measures::MouthOcclusionPrevention Class Reference

Implementation of the mouth occlusion prevention measure.

```
#include <MouthOcclusionPrevention.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::MouthOcclusionPrevention:



Public Member Functions

- [MouthOcclusionPrevention](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses absence of mouth occlusion.

Public Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.33.1 Detailed Description

Implementation of the mouth occlusion prevention measure.

Absence of mouth occlusion is assessed by measuring the coverage of the mouth region from mouth landmarks with the result of face occlusion segmentation computed on pre-processing.

7.33.2 Constructor & Destructor Documentation

7.33.2.1 MouthOcclusionPrevention()

```
OFIQ_LIB::modules::measures::MouthOcclusionPrevention::MouthOcclusionPrevention (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.33.3 Member Function Documentation

7.33.3.1 Execute()

```
void OFIQ_LIB::modules::measures::MouthOcclusionPrevention::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses absence of mouth occlusion.

Absence of mouth occlusion is assessed by measuring the coverage of the mouth region from mouth landmarks with the result of face occlusion segmentation computed on pre-processing. Pre-processing results are passed to the method with the `session` parameter.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

See also

- [FaceOcclusionSegmentation](#)
- [Session::getAlignedFaceLandmarks\(\)](#)

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [MouthOcclusionPrevention.h](#)

7.34 OFIQ_LIB::modules::measures::NaturalColour Class Reference

Implementation of the natural colour measure.

```
#include <NaturalColour.h>
```

Inheritance diagram for `OFIQ_LIB::modules::measures::NaturalColour`:



Public Member Functions

- [NaturalColour](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses natural colourness.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Member Functions

- cv::Mat [CreateMaskedImage](#) (const [OFIQ::FaceLandmarks](#) &landmarks, const cv::Mat &cvImage)
Creates a mask image from the convex hull of the specified landmarks.
- cv::Mat [ReduceImageToRegionOfInterest](#) (const cv::Mat &maskedImage, const cv::Rect &leftRegionOfInterest, const cv::Rect &rightRegionOfInterest)
Extracts two rectangular regions from an image and returns its concatenation.
- double [CalculateScore](#) (double meanChannelA, double meanChannelB)
Combines two CIELAB values a and b* to compute the native quality score.*

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & `configuration`

Reference to the configuration with which the measure constructor has been invoked.

7.34.1 Detailed Description

Implementation of the natural colour measure.

Assessment of the naturalness of the colour based on the conversion of the RGB presentation of the image to the CIELAB colour space.

7.34.2 Constructor & Destructor Documentation

7.34.2.1 NaturalColour()

```
OFIQ_LIB::modules::measures::NaturalColour::NaturalColour (
    const Configuration & configuration,
    Session & session )
```

Constructor.

Parameters

<code>configuration</code>	Configuration object from which measure-related configuration is read.
<code>session</code>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.34.3 Member Function Documentation

7.34.3.1 CalculateScore()

```
double OFIQ_LIB::modules::measures::NaturalColour::CalculateScore (
    double meanChannelA,
    double meanChannelB ) [private]
```

Combines two CIELAB values a^* and b^* to computed the native quality score.

If a^* and b^* are both larger than or equals to 0, then the following formula is applied

$$D = \sqrt{\max(\max(0, 5 - a^*), \max(0, a^* - 25))^2 + \max(\max(0, 5 - b^*), \max(b^* - 35))^2}$$

and D is returned; otherwise, the value 100 is returned.

Parameters

<code>meanChannelA</code>	The CIELAB value a^* input value.
<code>meanChannelB</code>	The CIELAB value b^* input value.

Returns

Native quality score

7.34.3.2 CreateMaskedImage()

```
cv::Mat OFIQ_LIB::modules::measures::NaturalColour::CreateMaskedImage (
    const OFIQ::FaceLandmarks & landmarks,
    const cv::Mat & cvImage ) [private]
```

Creates a mask image from the convex full of the specified landmarks.

Parameters

<i>landmarks</i>	Facial landmarks.
<i>cvImage</i>	The mask image returned has the same dimension as <i>cvImage</i> .

Returns

Mask image

7.34.3.3 Execute()

```
void OFIQ_LIB::modules::measures::NaturalColour::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses natural colourness.

Assessment of the naturalness of the colour based on the conversion of the RGB presentation of the image to the CIELAB colour space.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.34.3.4 ReduceImageToRegionOfInterest()

```
cv::Mat OFIQ_LIB::modules::measures::NaturalColour::ReduceImageToRegionOfInterest (
    const cv::Mat maskedImage,
    const cv::Rect & leftRegionOfInterest,
    const cv::Rect & rightRegionOfInterest ) [private]
```

Extracts two rectangular regions from an image and returns its concatenation.

Parameters

<i>maskedImage</i>	The input image from which the two regions are extracted.
<i>leftRegionOfInterest</i>	First region
<i>rightRegionOfInterest</i>	Second region

Returns

Concatenation if the requested regions; the first columns correspond to `rightRegionOfInterest` and the last columns correspond to `leftRegionOfInterest`.

Attention

An error occurs if the height of the two requested regions differ.

The documentation for this class was generated from the following file:

- [NaturalColour.h](#)

7.35 OFIQ_LIB::NeuronalNetworkContainer Struct Reference

Neural network container for OFIQ's preprocessing steps.

```
#include <NeuronalNetworkContainer.h>
```

Public Member Functions

- [NeuronalNetworkContainer](#) (`std::shared_ptr< FaceDetectorInterface > faceDetector`, `std::shared_ptr< FaceLandmarkExtractorInterface > landmarkExtractor`, `std::shared_ptr< SegmentationExtractorInterface > segmentationExtractor`, `std::shared_ptr< PoseEstimatorInterface > poseEstimator`, `std::shared_ptr< SegmentationExtractorInterface > faceOcclusionExtractor`)

Constructor.

Public Attributes

- `std::shared_ptr< FaceDetectorInterface > faceDetector`
Pointer to a [FaceDetectorInterface](#) .
- `std::shared_ptr< FaceLandmarkExtractorInterface > landmarkExtractor`
Pointer to a [FaceLandmarkExtractorInterface](#) .
- `std::shared_ptr< SegmentationExtractorInterface > segmentationExtractor`
Pointer to a [SegmentationExtractorInterface](#) .
- `std::shared_ptr< SegmentationExtractorInterface > faceOcclusionExtractor`
Pointer to a [SegmentationExtractorInterface](#) .
- `std::shared_ptr< PoseEstimatorInterface > poseEstimator`
Pointer to a [SegmentationExtractorInterface](#) .

7.35.1 Detailed Description

Neural network container for OFIQ's preprocessing steps.

7.35.2 Constructor & Destructor Documentation

7.35.2.1 NeuronalNetworkContainer()

```
OFIQ_LIB::NeuronalNetworkContainer::NeuronalNetworkContainer (
    std::shared_ptr< FaceDetectorInterface > faceDetector,
    std::shared_ptr< FaceLandmarkExtractorInterface > landmarkExtractor,
    std::shared_ptr< SegmentationExtractorInterface > segmentationExtractor,
    std::shared_ptr< PoseEstimatorInterface > poseEstimator,
    std::shared_ptr< SegmentationExtractorInterface > faceOcclusionExtractor ) [inline]
```

Constructor.

Parameters

<i>faceDetector</i>	Implementation of a FaceDetectorInterface
<i>landmarkExtractor</i>	Implementation of a FaceLandmarkExtractorInterface
<i>segmentationExtractor</i>	Implementation of a SegmentationExtractorInterface . A pointer to an object instantiated from the FaceParsing class would be valid.
<i>poseEstimator</i>	Implementation of a PoseEstimatorInterface
<i>faceOcclusionExtractor</i>	Implementation of a SegmentationExtractorInterface . A pointer to an object instantiated from the FaceOcclusionSegmentation class would be valid.

7.35.3 Member Data Documentation

7.35.3.1 faceDetector

```
std::shared_ptr<FaceDetectorInterface> OFIQ_LIB::NeuronalNetworkContainer::faceDetector
```

Pointer to a [FaceDetectorInterface](#) .

7.35.3.2 faceOcclusionExtractor

```
std::shared_ptr<SegmentationExtractorInterface> OFIQ_LIB::NeuronalNetworkContainer::faceOcclusionExtractor
```

Pointer to a [SegmentationExtractorInterface](#) .

A pointer to an object instantiated from the [FaceOcclusionSegmentation](#) class would be valid.

7.35.3.3 landmarkExtractor

```
std::shared_ptr<FaceLandmarkExtractorInterface> OFIQ_LIB::NeuronalNetworkContainer::landmarkExtractor
```

Pointer to a [FaceLandmarkExtractorInterface](#) .

7.35.3.4 poseEstimator

```
std::shared_ptr<PoseEstimatorInterface> OFIQ_LIB::NeuronalNetworkContainer::poseEstimator
```

Pointer to a [SegmentationExtractorInterface](#) .

7.35.3.5 segmentationExtractor

```
std::shared_ptr<SegmentationExtractorInterface> OFIQ_LIB::NeuronalNetworkContainer::segmentationExtractor
```

Pointer to a [SegmentationExtractorInterface](#) .

A pointer to an object instantiated from the [FaceParsing](#) class would be valid.

The documentation for this struct was generated from the following file:


- [NeuronalNetworkContainer.h](#)

7.36 OFIQ_LIB::modules::measures::NoHeadCoverings Class Reference

Implementation of the no head covering measure.

```
#include <NoHeadCoverings.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::NoHeadCoverings:



Public Member Functions

- [NoHeadCoverings](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Assesses no head covering.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Attributes

- double [threshold](#)
Threshold.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.36.1 Detailed Description

Implementation of the no head covering measure.

The face parsing pre-processing assigns all pixels on the aligned image to one class each encoded by a value between 0 and 19 (inclusively). The values 16 and 18 encode the class *clothing* and *head covering*, respectively. Assessment of no head covering is done on the base of counting all pixels classified as clothing and head covering on the upper part of the aligned facial image and dividing it by the number of all pixels in the aligned image. The ratio is the native quality score. If it exceeds a configurable threshold, a quality the quality component value 0 is used; otherwise, if the ratio is below (or equals) the threshold, a quality of 100 is used.

See also

[FaceParsing](#)

7.36.2 Constructor & Destructor Documentation

7.36.2.1 NoHeadCoverings()

```
OFIQ_LIB::modules::measures::NoHeadCoverings::NoHeadCoverings (
    const Configuration & configuration,
    Session & session )
```

Constructor.

The configuration object can optionally configure the threshold using the `params.measures.NoHeadCoverings.threshold` key which is 0.02 by default.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.36.3 Member Function Documentation

7.36.3.1 Execute()

```
void OFIQ_LIB::modules::measures::NoHeadCoverings::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Assesses no head covering.

The face parsing pre-processing assigns all pixels on the aligned image to one class each encoded by a value between 0 and 19 (inclusively). The values 16 and 18 encode the class *clothing* and *head covering*, respectively. Assessment of no head covering is done on the base of counting all pixels classified as clothing and head covering on the upper part of the aligned facial image and dividing it by the number of all pixels in the aligned image. The ratio is the native quality score. If it exceeds a configurable threshold, a quality the quality component value 0 is used; otherwise, if the ratio is below (or equals) the threshold, a quality of 100 is used.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

See also

[FaceParsing](#)

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.36.4 Member Data Documentation

7.36.4.1 threshold

```
double OFIQ_LIB::modules::measures::NoHeadCoverings::threshold [private]
```

Threshold.

If the native quality score (number of pixels classified as head covering divided by the number of total number of pixels in the aligned image), is below (or equals) this threshold, then a quality of 100 (best) is used; otherwise, a quality of 0 is used.

The documentation for this class was generated from the following file:


- [NoHeadCoverings.h](#)

7.37 OFIQ_LIB::OFIQError Class Reference

Implementation of a custom exception.

```
#include <OFIQError.h>
```

Inheritance diagram for OFIQ_LIB::OFIQError:



Public Member Functions

- [OFIQError](#) ([OFIQ::ReturnCode](#) `returnCode`, `std::string_view` `message`)
Constructor.
- `const char * what ()` `const` `noexcept` override
Getter to the message, overwriting the what method of the base class.
- [OFIQ::ReturnCode](#) `whatCode ()` `const` `noexcept`
Getter to the ReturnCode of the QFIQError.

Private Attributes

- [OFIQ::ReturnCode](#) `returnCode`
Member storing the ReturnCode.
- `std::string` `message`
Member, storing the message passed in the constructor.
- `std::string` `extendedMessage`
The extended message merges the ReturnCode and the message into one string.

7.37.1 Detailed Description

Implementation of a custom exception.

This exception is derived from the standard exception.

7.37.2 Constructor & Destructor Documentation

7.37.2.1 OFIQError()

```
OFIQ_LIB::OFIQError::OFIQError (
    OFIQ::ReturnCode returnCode,
    std::string_view message )
```

Constructor.

Parameters

<i>returnCode</i>	Based on the OFIQ::ReturnCode (see OFIQ::ReturnCode).
<i>message</i>	Message that will be attached to exception.

7.37.3 Member Function Documentation

7.37.3.1 what()

```
const char * OFIQ_LIB::OFIQError::what ( ) const [inline], [override], [noexcept]
```

Getter to the message, overwriting the what method of the base class.

Returns

const char* Pointer to the extended message.

7.37.3.2 whatCode()

```
OFIQ::ReturnCode OFIQ_LIB::OFIQError::whatCode ( ) const [inline], [noexcept]
```

Getter to the ReturnCode of the QFIQError.

Returns

OFIQ::ReturnCode

7.37.4 Member Data Documentation**7.37.4.1 extendedMessage**

```
std::string OFIQ_LIB::OFIQError::extendedMessage [private]
```

The extended message merges the ReturnCode and the message into one string.

7.37.4.2 message

```
std::string OFIQ_LIB::OFIQError::message [private]
```

Member, storing the message passed in the constructor.

7.37.4.3 returnCode

```
OFIQ::ReturnCode OFIQ_LIB::OFIQError::returnCode [private]
```

Member storing the ReturnCode.

The documentation for this class was generated from the following file:


- [OFIQError.h](#)

7.38 OFIQ_LIB::OFIQImpl Class Reference

Implementation of the OFIQ_LIB.

```
#include <ofiq_lib_impl.h>
```

Inheritance diagram for OFIQ_LIB::OFIQImpl:



Public Member Functions

- [OFIQImpl](#) ()
Constructor.
- [~OFIQImpl](#) () override=default
Destructor.
- [OFIQ::ReturnStatus initialize](#) (const std::string &configDir, const std::string &configValue) override
Initialize the lib by reading the configuration file.
- [OFIQ::ReturnStatus scalarQuality](#) (const [OFIQ::Image](#) &face, double &quality) override
Compute an overall quality score for the image provided.
- [OFIQ::ReturnStatus vectorQuality](#) (const [OFIQ::Image](#) &image, [OFIQ::FaceImageQualityAssessment](#) &assessments) override
Run the computation of all measures set in the configuration.

Public Member Functions inherited from [OFIQ::Interface](#)

- virtual [~Interface](#) ()=default
Default Destructor.

Private Member Functions

- std::unique_ptr< [OFIQ_LIB::modules::measures::Executor](#) > [CreateExecutor](#) ([Session](#) &session)
Create a Executor object.
- void [CreateNetworks](#) ()
Create a NeuronalNetworkContainer.
- void [performPreprocessing](#) ([Session](#) &session)
Perform the preprocessing.
- void [alignFacelImage](#) ([Session](#) &session)
Perform the face alignment.

Private Attributes

- std::unique_ptr< [OFIQ_LIB::modules::measures::Executor](#) > [m_executorPtr](#)
Pointer to the executor instance, see [OFIQ_LIB::modules::measures::Executor](#).
- [OFIQ::FaceImageQualityAssessment](#) [dummyAssesment](#)
required to suit Session constructor
- [OFIQ::Image](#) [dummyImage](#)
required to suit Session constructor
- [OFIQ_LIB::Session](#) [m_emptySession](#)
required to suit Session constructor
- std::unique_ptr< [Configuration](#) > [config](#)
Pointer to the cinfiguration.
- std::unique_ptr< [NeuronalNetworkContainer](#) > [networks](#)
Pointer to the different neural network instances, used during the preprocesing.

Additional Inherited Members

Static Public Member Functions inherited from [OFIQ::Interface](#)

- static [OFIQ_EXPORT](#) std::shared_ptr< [Interface](#) > [getImplementation](#) ()
Factory method to return a shared pointer to the Interface object.

7.38.1 Detailed Description

Implementation of the OFIQ_LIB.

7.38.2 Constructor & Destructor Documentation

7.38.2.1 OFIQImpl()

```
OFIQ_LIB::OFIQImpl::OFIQImpl ( )
```

Constructor.

7.38.2.2 ~OFIQImpl()

```
OFIQ_LIB::OFIQImpl::~~OFIQImpl ( ) [override], [default]
```

Destructor.

7.38.3 Member Function Documentation

7.38.3.1 alignFaceImage()

```
void OFIQ_LIB::OFIQImpl::alignFaceImage (
    Session & session ) [private]
```

Perform the face alignment.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
----------------	--

7.38.3.2 CreateExecutor()

```
std::unique_ptr< OFIQ\_LIB::modules::measures::Executor > OFIQ_LIB::OFIQImpl::CreateExecutor (
    Session & session ) [private]
```

Create a Executor object.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
----------------	--

Returns

std::unique_ptr<OFIQ_LIB::modules::measures::Executor>

7.38.3.3 CreateNetworks()

```
void OFIQ_LIB::OFIQImpl::CreateNetworks ( ) [private]
```

Create a NeuronalNetworkContainer.

7.38.3.4 initialize()

```
OFIQ::ReturnStatus OFIQ_LIB::OFIQImpl::initialize (
    const std::string & configDir,
    const std::string & configValue ) [override], [virtual]
```

Initialize the lib by reading the configuration file.

Parameters

<i>configDir</i>	Path to the configuration file.
<i>configValue</i>	Name of the configuration file.

Returns

OFIQ::ReturnStatus

Implements [OFIQ::Interface](#).

7.38.3.5 performPreprocessing()

```
void OFIQ_LIB::OFIQImpl::performPreprocessing (
    Session & session ) [private]
```

Perform the preprocessing.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
----------------	--

7.38.3.6 scalarQuality()

```
OFIQ::ReturnStatus OFIQ_LIB::OFIQImpl::scalarQuality (
    const OFIQ::Image & face,
    double & quality ) [override], [virtual]
```

Compute an overall quality score for the image provided.

The overall quality score will be equal to the measure `ualityMeasure::UnifiedQualityScore` if it is activated. Otherwise, the overall quality score will be the mean of all active measure scores.

Parameters

in	<i>face</i>	Input image.
out	<i>quality</i>	Computed UnifiedQualityScore.

Returns

OFIQ::ReturnStatus

Implements [OFIQ::Interface](#).

7.38.3.7 vectorQuality()

```
OFIQ::ReturnStatus OFIQ_LIB::OFIQImpl::vectorQuality (
    const OFIQ::Image & image,
    OFIQ::FaceImageQualityAssessment & assessments ) [override], [virtual]
```

Run the computation of all measures set in the configuration.

Parameters

in	<i>image</i>	Input image.
out	<i>assessments</i>	Container to store the resulting scores.

Returns

OFIQ::ReturnStatus

Implements [OFIQ::Interface](#).

7.38.4 Member Data Documentation

7.38.4.1 config

```
std::unique_ptr<Configuration> OFIQ_LIB::OFIQImpl::config [private]
```

Pointer to the configuration.

7.38.4.2 dummyAssesment

```
OFIQ::FaceImageQualityAssessment OFIQ_LIB::OFIQImpl::dummyAssesment [private]
```

required to suit Session constructor

7.38.4.3 dummyImage

`OFIQ::Image` `OFIQ_LIB::OFIQImpl::dummyImage` [private]

required to suit Session constructor

7.38.4.4 m_emptySession

`OFIQ_LIB::Session` `OFIQ_LIB::OFIQImpl::m_emptySession` [private]

required to suit Session constructor

7.38.4.5 m_executorPtr

`std::unique_ptr<OFIQ_LIB::modules::measures::Executor>` `OFIQ_LIB::OFIQImpl::m_executorPtr` [private]

Pointer to the executor instance, see [OFIQ_LIB::modules::measures::Executor](#).

7.38.4.6 networks

`std::unique_ptr<NeuronalNetworkContainer>` `OFIQ_LIB::OFIQImpl::networks` [private]

Pointer to the different neural network instances, used during the preprocessing.

The documentation for this class was generated from the following file:

- [ofiq_lib_impl.h](#)

7.39 ONNXRuntimeSegmentation Class Reference

Helper class to manage the ONNXRuntime session object.

```
#include <ONNXRTSegmentation.h>
```

Public Member Functions

- [ONNXRuntimeSegmentation](#) ()=default
Constructor.
- [~ONNXRuntimeSegmentation](#) ()=default
Destructor.
- void [initialize](#) (const std::vector< uint8_t > &i_modelData, int64_t i_imageWidth, int64_t i_imageHeight)
Public method to generate an ONNXRuntime session object.
- size_t [getNumberOfOutputNodes](#) ()
Get the number of output nodes (results) based on the loaded model.
- std::vector< Ort::Value > [run](#) (std::vector< float > &i_netInput)
Perform the computation.

Private Member Functions

- void `init_session` (const std::vector< uint8_t > &i_model_data, int64_t i_imageWidth, int64_t i_imageHeight)
Private method to generate an ONNXRuntime session object.

Private Attributes

- Ort::Env `m_ortenv`
Handle to the ONNXRuntime environment variable.
- Ort::MemoryInfo `m_memory_info` = Ort::MemoryInfo::CreateCpu(OrtDeviceAllocator, OrtMemTypeCPU)
ONNXRuntime variable to setup the tensors used in ONNXRuntime.
- std::array< int64_t, 4 > `m_inputShape`
Description of the shape of the input data expected by the model.
- std::unique_ptr< Ort::Session > `m_ort_session`
Handle to the ONNXRuntime session.

7.39.1 Detailed Description

Helper class to manage the ONNXRuntime session object.

Helper class to manage the ONNXRuntime session object. Details can be found on the ONNXRuntime documentation <https://onnxruntime.ai/docs/get-started/with-cpp.html>.

7.39.2 Constructor & Destructor Documentation

7.39.2.1 ONNXRuntimeSegmentation()

```
ONNXRuntimeSegmentation::ONNXRuntimeSegmentation ( ) [default]
```

Constructor.

7.39.2.2 ~ONNXRuntimeSegmentation()

```
ONNXRuntimeSegmentation::~~ONNXRuntimeSegmentation ( ) [default]
```

Destructor.

7.39.3 Member Function Documentation

7.39.3.1 getNumberOfOutputNodes()

```
size_t ONNXRuntimeSegmentation::getNumberOfOutputNodes ( )
```

Get the number of output nodes (results) based on the loaded model.

Returns

size_t number of output nodes (results).

7.39.3.2 init_session()

```
void ONNXRuntimeSegmentation::init_session (
    const std::vector< uint8_t > &i_model_data,
    int64_t i_imageWidth,
    int64_t i_imageHeight ) [private]
```

Private method to generate an ONNXRuntime session object.

Parameters

<i>i_model_data</i>	Model data loaded from file.
<i>i_imageWidth</i>	Width of the input image as expected by the model.
<i>i_imageHeight</i>	Height of the input image as expected by the model.

7.39.3.3 initialize()

```
void ONNXRuntimeSegmentation::initialize (
    const std::vector< uint8_t > & i_modelData,
    int64_t i_imageWidth,
    int64_t i_imageHeight )
```

Public method to generate an ONNXRuntime session object.

Parameters

<i>i_modelData</i>	Model data loaded from file.
<i>i_imageWidth</i>	Width of the input image as expected by the model.
<i>i_imageHeight</i>	Height of the input image as expected by the model.

7.39.3.4 run()

```
std::vector< Ort::Value > ONNXRuntimeSegmentation::run (
    std::vector< float > & i_netInput )
```

Perform the computation.

Parameters

<i>i_netInput</i>	Input to the neural net.
-------------------	--------------------------

Returns

std::vector<Ort::Value> Result of the neural net computation.

7.39.4 Member Data Documentation**7.39.4.1 m_inputShape**

```
std::array<int64_t, 4> ONNXRuntimeSegmentation::m_inputShape [private]
```

Description of the shape of the input data expected by the model.

7.39.4.2 m_memory_info

```
Ort::MemoryInfo ONNXRuntimeSegmentation::m_memory_info = Ort::MemoryInfo::CreateCpu(Ort↵
DeviceAllocator, OrtMemTypeCPU) [private]
```

ONNXRuntime variable to setup the tensors used in ONNXRuntime.

7.39.4.3 m_ort_session

```
std::unique_ptr<Ort::Session> ONNXRuntimeSegmentation::m_ort_session [private]
```

Handle to the ONNXRuntime session.

7.39.4.4 m_ortenv

```
Ort::Env ONNXRuntimeSegmentation::m_ortenv [private]
```

Handle to the ONNXRuntime environment variable.

The documentation for this class was generated from the following file:


- [ONNXRTSegmentation.h](#)

7.40 OFIQ_LIB::modules::measures::OverExposurePrevention Class Reference

Implementation of the over-exposure prevention measure.

```
#include <OverExposurePrevention.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::OverExposurePrevention:



Public Member Functions

- [OverExposurePrevention](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor a new Over Exposure Prevention.
- void [Execute](#) (OFIQ_LIB::Session &session) override
Run the computation of the over-exposure prevention measure.

Public Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from OFIQ_LIB::modules::measures::Measure

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from OFIQ_LIB::modules::measures::Measure

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.40.1 Detailed Description

Implementation of the over-exposure prevention measure.

The representation of a face is considered is light if it has a high proportion of pixels that have a high luminance value i.e. hot spots

7.40.2 Constructor & Destructor Documentation

7.40.2.1 OverExposurePrevention()

```
OFIQ_LIB::modules::measures::OverExposurePrevention::OverExposurePrevention (
    const Configuration & configuration,
    Session & session )
```

Constructor a new Over Exposure Prevention.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.40.3 Member Function Documentation

7.40.3.1 Execute()

```
void OFIQ_LIB::modules::measures::OverExposurePrevention::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Run the computation of the over-exposure prevention measure.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:

- [OverExposurePrevention.h](#)

7.41 OFIQ_LIB::modules::landmarks::PartExtractor Class Reference

Class that provides helper methods for the administration of landmarks.

```
#include <PartExtractor.h>
```

Static Public Member Functions

- static [OFIQ::Landmarks](#) [getFacePart](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, [FaceParts](#) part)

Extract the landmarks that correspondend to the requested face part out of a set of provided landmarks.
- static std::vector< [LandmarkPair](#) > [getPairsForPart](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, [FaceParts](#) part)

Get LandmarkPairs for a face part.

7.41.1 Detailed Description

Class that provides helper methods for the administration of landmarks.

7.41.2 Member Function Documentation

7.41.2.1 getFacePart()

```
static OFIQ::Landmarks OFIQ_LIB::modules::landmarks::PartExtractor::getFacePart (
    const OFIQ::FaceLandmarks & faceLandmarks,
    FaceParts part ) [static]
```

Extract the landmarks that correspondend to the requested face part out of a set of provided landmarks.

Parameters

<i>in</i>	<i>faceLandmarks</i>	Landmarks to be filtered.
	<i>part</i>	Face part of interest.

Returns

OFIQ::Landmarks Filtered landmarks that belong to the requested face part.

7.41.2.2 getPairsForPart()

```
static std::vector< LandmarkPair > OFIQ_LIB::modules::landmarks::PartExtractor::getPairsForPart (
    const OFIQ::FaceLandmarks & faceLandmarks,
    FaceParts part ) [static]
```

Get LandmarkPairs for a face part.

LandmarkPairs might be used to compute a distance between upper and lower landmark.

Parameters

<i>faceLandmarks</i>	Set of face landmarks.
<i>part</i>	Face part of interest.

Returns

std::vector<LandmarkPair>

The documentation for this class was generated from the following file:

- [PartExtractor.h](#)

7.42 Point2f Struct Reference

Representation of a point with floating point arithmetics.

```
#include <utils.h>
```

Public Attributes

- float *x*
- float *y*

7.42.1 Detailed Description

Representation of a point with floating point arithmetics.

7.42.2 Member Data Documentation

7.42.2.1 x

```
float Point2f::x
```

7.42.2.2 y

```
float Point2f::y
```

The documentation for this struct was generated from the following file:

- [utils.h](#)

7.43 OFIQ_LIB::Point2i Struct Reference

Representation of a point with integer arithmetics.

```
#include <utils.h>
```

Public Attributes

- [int x](#)
- [int y](#)

7.43.1 Detailed Description

Representation of a point with integer arithmetics.

7.43.2 Member Data Documentation

7.43.2.1 x

```
int OFIQ_LIB::Point2i::x
```

7.43.2.2 y

```
int OFIQ_LIB::Point2i::y
```

The documentation for this struct was generated from the following file:


- [utils.h](#)

7.44 OFIQ_LIB::PoseEstimatorInterface Class Reference

Implementation of the base class for integrating pose estimation algorithms capable of estimating three head orientation angles (yaw, pitch and roll) from a face image.

```
#include <poseEstimators.h>
```

Inheritance diagram for OFIQ_LIB::PoseEstimatorInterface:



Public Types

- using [EulerAngle](#) = `std::array<double, 3>`

Public Member Functions

- virtual `~PoseEstimatorInterface()`=default
Standard destructor.
- [EulerAngle](#) & `estimatePose` ([OFIQ_LIB::Session](#) &session)
This function estimates the three head orientation angles.

Protected Member Functions

- virtual void `updatePose` ([OFIQ_LIB::Session](#) &session, [EulerAngle](#) &pose)=0
Call to estimate the head orientations. Has to be implemented in the derived class.

Private Attributes

- `std::string` [lastSessionId](#)
id of the session that has been used in the latest request, for internal use.
- [EulerAngle](#) [pose](#)
Container for storing the estimated head orientations.

7.44.1 Detailed Description

Implementation of the base class for integrating pose estimation algorithms capable of estimating three head orientation angles (yaw, pitch and roll) from a face image.

7.44.2 Member Typedef Documentation

7.44.2.1 EulerAngle

```
using OFIQ_LIB_PoseEstimatorInterface_EulerAngle = std::array<double, 3>
```

7.44.3 Constructor & Destructor Documentation

7.44.3.1 ~PoseEstimatorInterface()

```
virtual OFIQ_LIB::PoseEstimatorInterface::~~PoseEstimatorInterface ( ) [virtual], [default]
```

Standard destructor.

7.44.4 Member Function Documentation

7.44.4.1 estimatePose()

```
EulerAngle & OFIQ_LIB::PoseEstimatorInterface::estimatePose (
    OFIQ_LIB::Session & session )
```

This function estimates the three head orientation angles.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
----------------	--

7.44.4.2 updatePose()

```
virtual void OFIQ_LIB::PoseEstimatorInterface::updatePose (
    OFIQ_LIB::Session & session,
    EulerAngle & pose ) [protected], [pure virtual]
```

Call to estimate the head orientations. Has to be implemented in the derived class.

Parameters

<i>session</i>	Containing the input image for the estimation.
<i>pose</i>	Return the estimated pose.

Implemented in [OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2](#).

7.44.5 Member Data Documentation

7.44.5.1 lastSessionId

```
std::string OFIQ_LIB::PoseEstimatorInterface::lastSessionId [private]
```

id of the session that has been used in the latest request, for internal use.

7.44.5.2 pose

`EulerAngle` OFIQ_LIB::PoseEstimatorInterface::pose [private]

Container for storing the estimated head orientations.

The documentation for this class was generated from the following file:

- [poseEstimators.h](#)

7.45 OFIQ::QualityMeasureResult Struct Reference

Data structure to handle the results of a quality measure.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [QualityMeasureResult](#) ()=default
Default constructor.
- [QualityMeasureResult](#) (double `rawScore`, double `scalar`=-1, [QualityMeasureReturnCode](#) `code`=[QualityMeasureReturnCode::NotInitialized](#))
Parameterized constructor.

Public Attributes

- double `rawScore` { -1 }
Raw value as computed by the quality measure implementation.
- double `scalar` { -1 }
A scalar value from the interval [0,100] Higher values mean higher quality. A value of -1.0 indicates a failed attempt to calculate a quality score or the value is unassigned.
- [QualityMeasureReturnCode](#) `code` { [QualityMeasureReturnCode::NotInitialized](#) }
Return status code.

7.45.1 Detailed Description

Data structure to handle the results of a quality measure.

7.45.2 Constructor & Destructor Documentation

7.45.2.1 QualityMeasureResult() [1/2]

```
OFIQ::QualityMeasureResult::QualityMeasureResult ( ) [default]
```

Default constructor.

7.45.2.2 QualityMeasureResult() [2/2]

```
OFIQ::QualityMeasureResult::QualityMeasureResult (
    double rawScore,
    double scalar = -1,
    QualityMeasureReturnCode code = QualityMeasureReturnCode::NotInitialized ) [inline]
```

Parameterized constructor.

Parameters

in	<i>rawScore</i>	Computed raw score.
in	<i>scalar</i>	Computed scalar score.
in	<i>code</i>	QualityMeasureReturnCode describing the state of the computation.

7.45.3 Member Data Documentation

7.45.3.1 code

```
QualityMeasureReturnCode OFIQ::QualityMeasureResult::code { QualityMeasureReturnCode::NotInitialized
}
```

Return status code.

7.45.3.2 rawScore

```
double OFIQ::QualityMeasureResult::rawScore { -1 }
```

Raw value as computed by the quality measure implementation.

7.45.3.3 scalar

```
double OFIQ::QualityMeasureResult::scalar { -1 }
```

A scalar value from the interval [0,100] Higher values mean higher quality. A value of -1.0 indicates a failed attempt to calculate a quality score or the value is unassigned.

The documentation for this struct was generated from the following file:

- [ofiq_structs.h](#)

7.46 OFIQ::ReturnStatus Struct Reference

A structure to contain information about a failure by the software under test.

```
#include <ofiq_structs.h>
```

Public Member Functions

- [ReturnStatus](#) ()=default
Default constructor.
- [ReturnStatus](#) (const [ReturnCode](#) code, const std::string &info="")
Parameterized constructor.

Public Attributes

- [ReturnCode](#) `code` { [ReturnCode::UnknownError](#) }
Return status code.
- `std::string` `info`
Optional information string.

7.46.1 Detailed Description

A structure to contain information about a failure by the software under test.

An object of this class allows the software to return some information from a function call. The string within this object can be optionally set to provide more information for debugging etc. The status code will be set by the function to Success on success, or one of the other codes on failure.

7.46.2 Constructor & Destructor Documentation

7.46.2.1 ReturnStatus() [1/2]

```
OFIQ::ReturnStatus::ReturnStatus ( ) [default]
```

Default constructor.

7.46.2.2 ReturnStatus() [2/2]

```
OFIQ::ReturnStatus::ReturnStatus (
    const ReturnCode code,
    const std::string & info = "" ) [inline]
```

Parameterized constructor.

Parameters

<code>in</code>	<code>code</code>	The return status code; required.
<code>in</code>	<code>info</code>	The optional information string.

7.46.3 Member Data Documentation

7.46.3.1 code

```
ReturnCode OFIQ::ReturnStatus::code { ReturnCode::UnknownError }
```

Return status code.

7.46.3.2 info

```
std::string OFIQ::ReturnStatus::info
```

Optional information string.

The documentation for this struct was generated from the following file:


- [ofiq_structs.h](#)

7.47 OFIQ_LIB::SegmentationExtractorInterface Class Reference

Base class for the different implementation of segmentation algorithms.

```
#include <segmentations.h>
```

Inheritance diagram for OFIQ_LIB::SegmentationExtractorInterface:



Public Member Functions

- virtual `~SegmentationExtractorInterface()`=default
Standard destructor.
- `OFIQ::Image & GetMask (OFIQ_LIB::Session &session, modules::segmentations::SegmentClassLabels faceSegment)`
Get a mask of the face region requested.

Protected Member Functions

- virtual `OFIQ::Image UpdateMask (OFIQ_LIB::Session &session, modules::segmentations::SegmentClassLabels faceSegment)=0`
Segmentation call that has to be implemented in the derived class.
- `std::string GetLastSessionId () const`
Accesses the last session id for this interface.

Private Attributes

- `std::string lastSessionId`
id of the session that has been used in the latest request, for internal use.
- `std::map< modules::segmentations::SegmentClassLabels, OFIQ::Image > masks`
Container for storing the segmented face region masks.

7.47.1 Detailed Description

Base class for the different implementation of segmentation algorithms.

Base class for the FaceParsing (see [OFIQ_LIB::modules::segmentations::FaceParsing](#)) and FaceOcclusionSegmentation (see [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#))

7.47.2 Constructor & Destructor Documentation

7.47.2.1 ~SegmentationExtractorInterface()

```
virtual OFIQ_LIB::SegmentationExtractorInterface::~~SegmentationExtractorInterface ( ) [virtual],
[default]
```

Standard destructor.

7.47.3 Member Function Documentation

7.47.3.1 GetLastSessionId()

```
std::string OFIQ_LIB::SegmentationExtractorInterface::GetLastSessionId ( ) const [inline],
[protected]
```

Accesses the last session id for this interface.

Returns

Session id

7.47.3.2 GetMask()

```
OFIQ::Image & OFIQ_LIB::SegmentationExtractorInterface::GetMask (
    OFIQ_LIB::Session & session,
    modules::segmentations::SegmentClassLabels faceSegment )
```

Get a mask of the face region requested.

Parameters

<i>session</i>	Object containing the relevant data information on the input image.
<i>faceSegment</i>	Enum of the face region that is requested.

Returns

OFIQ::Image& Reference on the mask of the face region image.

7.47.3.3 UpdateMask()

```
virtual OFIQ::Image OFIQ_LIB::SegmentationExtractorInterface::UpdateMask (
    OFIQ_LIB::Session & session,
    modules::segmentations::SegmentClassLabels faceSegment ) [protected], [pure virtual]
```

Segmentation call that has to be implemented in the derived class.

Parameters

<i>session</i>	Object containing the relevant data information on the input image.
<i>faceSegment</i>	Enum of the face region that is requested

Returns

OFIQ::Image Segmented face region mask.

Implemented in [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#), and [OFIQ_LIB::modules::segmentations::FacePar](#)

7.47.4 Member Data Documentation

7.47.4.1 lastSessionId

```
std::string OFIQ_LIB::SegmentationExtractorInterface::lastSessionId [private]
```

id of the session that has been used in the latest request, for internal use.

7.47.4.2 masks

```
std::map<modules::segmentations::SegmentClassLabels, OFIQ::Image> OFIQ_LIB::Segmentation↔
ExtractorInterface::masks [private]
```

Container for storing the segmented face region masks.

The documentation for this class was generated from the following file:

- [segmentations.h](#)

7.48 OFIQ_LIB::Session Class Reference

```
#include <Session.h>
```

Public Member Functions

- [Session](#) (const [OFIQ::Image](#) &image, [OFIQ::FaceImageQualityAssessment](#) &assessment)
Construct a new Session object.
- const [OFIQ::Image](#) & image () const
Access reference to the input image, connected to this session.
- [OFIQ::FaceImageQualityAssessment](#) & assessment ()
Access reference to the FaceImageQualityAssessment object, connected to this session.
- const std::string & Id () const
Access to the id connected to this session.
- void [setDetectedFaces](#) (const std::vector< [OFIQ::BoundingBox](#) > &i_boundingBoxes)
Set the Detected Faces.
- std::vector< [OFIQ::BoundingBox](#) > [getDetectedFaces](#) () const
Get the Detected Faces.
- void [setPose](#) (const [EulerAngle](#) &i_pose)
Set the Pose of the input image.
- [EulerAngle](#) [getPose](#) () const
Get the Pose of the input image.
- void [setLandmarks](#) (const [OFIQ::FaceLandmarks](#) &i_landmarks)
Set the Landmarks detected on the input image.
- [OFIQ::FaceLandmarks](#) [getLandmarks](#) () const
Get the Landmarks detected on the input image.
- void [setAlignedFaceLandmarks](#) (const [OFIQ::FaceLandmarks](#) &i_landmarks)
Set the Aligned Face Landmarks detected on the aligned image.
- [OFIQ::FaceLandmarks](#) [getAlignedFaceLandmarks](#) () const
Get the Aligned Face Landmarks detected on the aligned image.
- void [setAlignedFaceTransformationMatrix](#) (const cv::Mat &i_transformationMatrix)
Set the Aligned Face Transformation Matrix.
- cv::Mat [getAlignedFaceTransformationMatrix](#) () const
Get the Aligned Face Transformation Matrix.
- void [setAlignedFace](#) (const cv::Mat &i_alignedFace)
Set the Aligned Face.
- cv::Mat [getAlignedFace](#) () const
Get the Aligned Face object.
- void [setAlignedFaceLandmarkedRegion](#) (const cv::Mat &i_alignedFaceRegion)
Set the Aligned Face Landmarked Region.
- cv::Mat [getAlignedFaceLandmarkedRegion](#) () const
Get the Aligned Face Landmarked Region.
- void [setFaceParsingImage](#) (const cv::Mat &i_parsingImage)
Set the Face Parsing Image, see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).
- cv::Mat [getFaceParsingImage](#) () const
Get the Face Parsing Image, see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).
- void [setFaceOcclusionSegmentationImage](#) (const cv::Mat &i_segmentationImage)
Set the Face Occlusion Segmentation Image, see [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#)).
- cv::Mat [getFaceOcclusionSegmentationImage](#) () const
Get the Face Occlusion Segmentation Image, see [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#)).

Private Member Functions

- std::string [GenerateId](#) () const
Method for generating uuid's for the session.

Private Attributes

- `const OFIQ::Image & _image`
Reference to the input image, connected to this session.
- `OFIQ::FaceImageQualityAssessment & _assessment`
Reference to the FaceImageQualityAssessment object, connected to this session.
- `std::vector< OFIQ::BoundingBox > detectedFaces`
Container for the faces found on the input image.
- `EulerAngle pose`
Container for storing the pose information.
- `OFIQ::FaceLandmarks landmarks`
Container for storing the landmark information.
- `OFIQ::FaceLandmarks alignedFaceLandmarks`
Container for storing the landmark information of the aligned image.
- `cv::Mat alignedFaceTransformationMatrix`
Container for storing the transformation matrix that led to the aligned image.
- `cv::Mat alignedFace`
Container for storing the aligned image.
- `cv::Mat alignedFacelandmarkedRegion`
Container for storing the landmarks of the aligned face image.
- `cv::Mat faceParsingImage`
Container for storing the segmented face image.
- `cv::Mat faceOcclusionSegmentationImage`
Container for storing the result of the face occlusion segmented image.
- `std::string id`
Container for storing the id of the session.

7.48.1 Detailed Description

`@brief` The session class is the data container used to distribute the image and additional data,

including the data computed during the pre-processing.

One instance of this class contains the relevant face information used for the computation of the activated measures. Most information is acquired during the pre-processing where the detection of the facial landmarks, the aligned image, etc. is computed.

7.48.2 Constructor & Destructor Documentation

7.48.2.1 Session()

```
OFIQ_LIB::Session::Session (
    const OFIQ::Image & image,
    OFIQ::FaceImageQualityAssessment & assessment ) [inline]
```

Construct a new Session object.

Parameters

<i>image</i>	Input image that shall be analysed.
<i>assessment</i>	Container to store the computed measures.

7.48.3 Member Function Documentation

7.48.3.1 assessment()

```
OFIQ::FaceImageQualityAssessment & OFIQ_LIB::Session::assessment ( ) [inline]
```

Access reference to the FaceImageQualityAssessment object, connected to this session.

Returns

quality assessment object reference.

7.48.3.2 GenerateId()

```
std::string OFIQ_LIB::Session::GenerateId ( ) const [private]
```

Method for generating uuid's for the session.

Returns

std::string

7.48.3.3 getAlignedFace()

```
cv::Mat OFIQ_LIB::Session::getAlignedFace ( ) const
```

Get the Aligned Face object.

Returns

cv::Mat

7.48.3.4 getAlignedFaceLandmarkedRegion()

```
cv::Mat OFIQ_LIB::Session::getAlignedFaceLandmarkedRegion ( ) const
```

Get the Aligned Face Landmarked Region.

Returns

cv::Mat

7.48.3.5 getAlignedFaceLandmarks()

```
OFIQ::FaceLandmarks OFIQ_LIB::Session::getAlignedFaceLandmarks ( ) const
```

Get the Aligned Face Landmarks detected on the aligned image.

Returns

OFIQ::FaceLandmarks

7.48.3.6 getAlignedFaceTransformationMatrix()

```
cv::Mat OFIQ_LIB::Session::getAlignedFaceTransformationMatrix ( ) const
```

Get the Aligned Face Transformation Matrix.

Returns

cv::Mat

7.48.3.7 getDetectedFaces()

```
std::vector< OFIQ::BoundingBox > OFIQ_LIB::Session::getDetectedFaces ( ) const
```

Get the Detected Faces.

Returns

std::vector<OFIQ::BoundingBox> Return the bounding boxes of faces found on the image.

7.48.3.8 getFaceOcclusionSegmentationImage()

```
cv::Mat OFIQ_LIB::Session::getFaceOcclusionSegmentationImage ( ) const
```

Get the Face Occlusion Segmentation Image, see [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#))

Returns

cv::Mat

7.48.3.9 getFaceParsingImage()

```
cv::Mat OFIQ_LIB::Session::getFaceParsingImage ( ) const
```

Get the Face Parsing Image, see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).

Returns

cv::Mat

7.48.3.10 getLandmarks()

```
OFIQ::FaceLandmarks OFIQ_LIB::Session::getLandmarks ( ) const
```

Get the Landmarks detected on the input image.

Returns

OFIQ::FaceLandmarks

7.48.3.11 getPose()

```
EulerAngle OFIQ_LIB::Session::getPose ( ) const
```

Get the Pose of the input image.

Returns

EulerAngle Pose of the ipnut image.

7.48.3.12 Id()

```
const std::string & OFIQ_LIB::Session::Id ( ) const [inline]
```

Access to the id connected to this session.

Returns

const std::string& Reference to the id of this session.

7.48.3.13 image()

```
const OFIQ::Image & OFIQ_LIB::Session::image ( ) const [inline]
```

Access reference to the input image, connected to this session.

Returns

input image reference.

7.48.3.14 setAlignedFace()

```
void OFIQ_LIB::Session::setAlignedFace (
    const cv::Mat & i_alignedFace )
```

Set the Aligned Face.

Parameters

<i>i_alignedFace</i>	
----------------------	--

7.48.3.15 setAlignedFaceLandmarkedRegion()

```
void OFIQ_LIB::Session::setAlignedFaceLandmarkedRegion (
    const cv::Mat & i_alignedFaceRegion )
```

Set the Aligned Face Landmarked Region.

Parameters

<i>i_alignedFaceRegion</i>	
----------------------------	--

7.48.3.16 setAlignedFaceLandmarks()

```
void OFIQ_LIB::Session::setAlignedFaceLandmarks (
    const OFIQ::FaceLandmarks & i_landmarks )
```

Set the Aligned Face Landmarks detected on the aligned image.

Parameters

<i>i_landmarks</i>	
--------------------	--

7.48.3.17 setAlignedFaceTransformationMatrix()

```
void OFIQ_LIB::Session::setAlignedFaceTransformationMatrix (
    const cv::Mat & i_transformationMatrix )
```

Set the Aligned Face Transformation Matrix.

Parameters

<i>i_transformationMatrix</i>	
-------------------------------	--

7.48.3.18 setDetectedFaces()

```
void OFIQ_LIB::Session::setDetectedFaces (
    const std::vector< OFIQ::BoundingBox > & i_boundingBoxes )
```

Set the Detected Faces.

Parameters

<i>i_boundingBoxes</i>	Vector of face bounding boxes found by a face detector.
------------------------	---

7.48.3.19 setFaceOcclusionSegmentationImage()

```
void OFIQ_LIB::Session::setFaceOcclusionSegmentationImage (
    const cv::Mat & i_segmentationImage )
```

Set the Face Occlusion Segmentation Image, see [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#))

Parameters

<i>i_segmentationImage</i>	
----------------------------	--

7.48.3.20 setFaceParsingImage()

```
void OFIQ_LIB::Session::setFaceParsingImage (
    const cv::Mat & i_parsingImage )
```

Set the Face Parsing Image, see [OFIQ_LIB::modules::segmentations::FaceParsing](#)).

Parameters

<i>i_parsingImage</i>	
-----------------------	--

7.48.3.21 setLandmarks()

```
void OFIQ_LIB::Session::setLandmarks (
    const OFIQ::FaceLandmarks & i_landmarks )
```

Set the Landmarks detected on the input image.

Parameters

<i>i_landmarks</i>	
--------------------	--

7.48.3.22 setPose()

```
void OFIQ_LIB::Session::setPose (
    const EulerAngle & i_pose )
```

Set the Pose of the input image.

Parameters

<code>i_pose</code>	
---------------------	--

7.48.4 Member Data Documentation

7.48.4.1 `_assessment`

```
OFIQ::FaceImageQualityAssessment& OFIQ_LIB::Session::_assessment [private]
```

Reference to the FaceImageQualityAssessment object, connected to this session.

7.48.4.2 `_image`

```
const OFIQ::Image& OFIQ_LIB::Session::_image [private]
```

Reference to the input image, connected to this session.

7.48.4.3 `alignedFace`

```
cv::Mat OFIQ_LIB::Session::alignedFace [private]
```

Container for storing the aligned image.

7.48.4.4 `alignedFacelandmarkedRegion`

```
cv::Mat OFIQ_LIB::Session::alignedFacelandmarkedRegion [private]
```

Container for storing the landmarks of the aligned face image.

7.48.4.5 `alignedFaceLandmarks`

```
OFIQ::FaceLandmarks OFIQ_LIB::Session::alignedFaceLandmarks [private]
```

Container for storing the landmark information of the aligned image.

7.48.4.6 `alignedFaceTransformationMatrix`

```
cv::Mat OFIQ_LIB::Session::alignedFaceTransformationMatrix [private]
```

Container for storing the transformation matrix that led to the aligned image.

7.48.4.7 detectedFaces

```
std::vector<OFIQ::BoundingBox> OFIQ_LIB::Session::detectedFaces [private]
```

Container for the faces found on the input image.

7.48.4.8 faceOcclusionSegmentationImage

```
cv::Mat OFIQ_LIB::Session::faceOcclusionSegmentationImage [private]
```

Container for storing the result of the face occlusion segmented image.

7.48.4.9 faceParsingImage

```
cv::Mat OFIQ_LIB::Session::faceParsingImage [private]
```

Container for storing the segmented face image.

7.48.4.10 id

```
std::string OFIQ_LIB::Session::id [private]
```

Container for storing the id of the session.

7.48.4.11 landmarks

```
OFIQ::FaceLandmarks OFIQ_LIB::Session::landmarks [private]
```

Container for storing the landmark information.

7.48.4.12 pose

```
EulerAngle OFIQ_LIB::Session::pose [private]
```

Container for storing the pose information.

The documentation for this class was generated from the following file:


- [Session.h](#)

7.49 OFIQ_LIB::modules::measures::Sharpness Class Reference

Implementation of the sharpness measure.

```
#include <Sharpness.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::Sharpness:



Public Member Functions

- [Sharpness](#) (const [Configuration](#) &configuration, [Session](#) &session)
Construct a new Sharpness object.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run computation of the sharpness measure.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Member Functions

- void [GetCroppedImages](#) ([Session](#) &session, cv::Mat &faceCrop, cv::Mat &maskCrop, bool [useAligned](#), float [faceRegionAlpha](#))
Get the cropped face region.
- cv::Mat [GetClassifierFocusFeatures](#) (cv::Mat &image, cv::Mat &mask, bool applyBlur)
Computation of the input features using different edge detectors.

Private Attributes

- std::string [modelFile](#)
Name of the random forest model, extracted from the configuration file.
- std::shared_ptr< cv::ml::RTrees > [rtree](#)
Instance of the random forest model.
- bool [useAligned](#)
The sharpness measure can be computed on the aligned or the original image. useAligned set to true will run the computation on the aligned image. The member is read from the configuration file.
- double [faceRegionAlpha](#)
For faceRegionAlpha = 0, the algorithm uses the inner face region. For faceRegionAlpha = 0.85, the algorithm uses the extended face region as specified for the FaceOcclusionin FRVT Quality.
- int [numTrees](#)
This member stores the number of trees used for the random forest. Internal use only.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & [configuration](#)
Reference to the configuration with which the measure constructor has been invoked.

7.49.1 Detailed Description

Implementation of the sharpness measure.

This quality component can be used to efficiently choose the better focused face portrait among several face samples of the same biometric capture subject. It should not be used to perform an absolute sharpness assessment if only one sample is available

7.49.2 Constructor & Destructor Documentation

7.49.2.1 Sharpness()

```
OFIQ_LIB::modules::measures::Sharpness::Sharpness (
    const Configuration & configuration,
    Session & session )
```

Construct a new Sharpness object.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.49.3 Member Function Documentation

7.49.3.1 Execute()

```
void OFIQ_LIB::modules::measures::Sharpness::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Run computation of the sharpness measure.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.49.3.2 GetClassifierFocusFeatures()

```
cv::Mat OFIQ_LIB::modules::measures::Sharpness::GetClassifierFocusFeatures (
    cv::Mat & image,
    cv::Mat & mask,
    bool applyBlur ) [private]
```

Computation of the input features using different edge detectors.

Parameters

<i>image</i>	Input image.
<i>mask</i>	Input region of the face.
<i>applyBlur</i>	Whether or not rub a GaussianBlur before the edge detection.

Returns

cv::Mat Container storing the results of the different edge detectors.

7.49.3.3 GetCroppedImages()

```
void OFIQ_LIB::modules::measures::Sharpness::GetCroppedImages (
    Session & session,
    cv::Mat & faceCrop,
    cv::Mat & maskCrop,
```

```
bool useAligned,
float faceRegionAlpha ) [private]
```

Get the cropped face region.

Parameters

<i>session</i>	Data container.
<i>faceCrop</i>	Computed crop of the face.
<i>maskCrop</i>	Mask used for the cropping. Will be computed in the method.
<i>useAligned</i>	Switch for using the aligned image.
<i>faceRegionAlpha</i>	Enlarge the face region by passing this parameter.

7.49.4 Member Data Documentation

7.49.4.1 faceRegionAlpha

```
double OFIQ_LIB::modules::measures::Sharpness::faceRegionAlpha [private]
```

For faceRegionAlpha = 0, the algorithm uses the inner face region. For faceRegionAlpha = 0.85, the algorithm uses the extended face region as specified for the FaceOcclusionin FRVT Quality.

7.49.4.2 modelFile

```
std::string OFIQ_LIB::modules::measures::Sharpness::modelFile [private]
```

Name of the random forest model, extracted from the configuration file.

7.49.4.3 numTrees

```
int OFIQ_LIB::modules::measures::Sharpness::numTrees [private]
```

This member stores the number of trees used for the random forest. Internal use only.

7.49.4.4 rtree

```
std::shared_ptr<cv::ml::RTrees> OFIQ_LIB::modules::measures::Sharpness::rtree [private]
```

Instance of the random forest model.

7.49.4.5 useAligned

```
bool OFIQ_LIB::modules::measures::Sharpness::useAligned [private]
```

The sharpness measure can be computed on the aligned or the original image. useAligned set to true will run the computation on the aligned image. The member is read from the configuration file.

The documentation for this class was generated from the following file:

- [Sharpness.h](#)

7.50 OFIQ_LIB::modules::measures::SigmoidParameters Struct Reference

Parameters of the sigmoid function based quality mapping.

```
#include <Measure.h>
```

Public Member Functions

- [SigmoidParameters](#) ()
Default constructor.
- void [setInverse](#) ()
Sets this quality mapping to a smaller-is-better variant.
- void [Reset](#) ()
Resets the members of the quality mapping to their default values.

Public Attributes

- double [h](#)
Scale factor.
- double [a](#)
Constant shift.
- double [s](#)
Signed weight for sigmoid part.
- double [x0](#)
Center point in sigmoid part.
- double [w](#)
Divisor in sigmoid part.
- bool [round](#)
Flag controlling if the compiler's native rounding function (`std::round`) is applied.

7.50.1 Detailed Description

Parameters of the sigmoid function based quality mapping.

A sigmoid-based quality mapping is the following function

$$Q(x) = h \cdot (a + s \cdot \text{sigmoid}(x, x_0, w))$$

where

$$\text{sigmoid}(x, x_0, w) = (1 + \exp((x_0 - x)/w))^{-1}.$$

Q can be used to map a native quality score x to a value between 0 and 100. The other symbols denote parameters that can be configured using the struct.

7.50.2 Constructor & Destructor Documentation

7.50.2.1 SigmoidParameters()

```
OFIQ_LIB::modules::measures::SigmoidParameters::SigmoidParameters ( ) [inline]
```

Default constructor.

After construction, all members are set to their default values.

7.50.3 Member Function Documentation

7.50.3.1 Reset()

```
void OFIQ_LIB::modules::measures::SigmoidParameters::Reset ( ) [inline]
```

Resets the members of the quality mapping to their default values.

7.50.3.2 setInverse()

```
void OFIQ_LIB::modules::measures::SigmoidParameters::setInverse ( ) [inline]
```

Sets this quality mapping to a smaller-is-better variant.

If the parameters a is 0 and s is, then this quality mapping is in larger-is-better-semantics. For those mappings, the method can be used to set the mapping to its smaller-is- better counterpart by setting a to 1 and s to -1. This is used by some measures to conveniently set a quality mapping.

7.50.4 Member Data Documentation

7.50.4.1 a

```
double OFIQ_LIB::modules::measures::SigmoidParameters::a
```

Constant shift.

The default value is 0.

7.50.4.2 h

```
double OFIQ_LIB::modules::measures::SigmoidParameters::h
```

Scale factor.

The default value is 100.

7.50.4.3 round

```
bool OFIQ_LIB::modules::measures::SigmoidParameters::round
```

Flag controlling if the compiler's native rounding function (`std::round`) is applied.

The default value is `true`.

7.50.4.4 s

```
double OFIQ_LIB::modules::measures::SigmoidParameters::s
```

Signed weight for sigmoid part.

The default value is 1.

7.50.4.5 w

```
double OFIQ_LIB::modules::measures::SigmoidParameters::w
```

Divisor in sigmoid part.

The default value of 0.7 has been chosen arbitrarily and should specified when a mapping is configured.

7.50.4.6 x0

```
double OFIQ_LIB::modules::measures::SigmoidParameters::x0
```

Center point in sigmoid part.

The default value of 4 has been chosen arbitrarily and should specified when a mapping is configured.

The documentation for this struct was generated from the following file:


- [Measure.h](#)

7.51 OFIQ_LIB::modules::measures::SingleFacePresent Class Reference

Implementation of the single face present measure.

```
#include <SingleFacePresent.h>
```

Inheritance diagram for `OFIQ_LIB::modules::measures::SingleFacePresent`:



Public Member Functions

- [SingleFacePresent](#) (const [Configuration](#) &configuration, [Session](#) &session)
Construct a new Single Face Present object.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run computation of the single face present analysis.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members**Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)**

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.51.1 Detailed Description

Implementation of the single face present measure.

Single face present measure shall ensure that only one face is visible on the image.

7.51.2 Constructor & Destructor Documentation

7.51.2.1 SingleFacePresent()

```
OFIQ_LIB::modules::measures::SingleFacePresent::SingleFacePresent (
    const Configuration & configuration,
    Session & session )
```

Construct a new Single Face Present object.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.51.3 Member Function Documentation

7.51.3.1 Execute()

```
void OFIQ_LIB::modules::measures::SingleFacePresent::Execute (
    OFIQ\_LIB::Session & session ) [override], [virtual]
```

Run computation of the single face present analysis.

Parameters

<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method
----------------	--

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [SingleFacePresent.h](#)

7.52 OFIQ_LIB::modules::detectors::SSDFaceDetector Class Reference

Implementation of a face detector using the SSD face detector CNN.

```
#include <opencv_ssd_face_detector.h>
```

Inheritance diagram for OFIQ_LIB::modules::detectors::SSDFaceDetector:



Public Member Functions

- [SSDFaceDetector](#) (const [Configuration](#) &config)
Constructor a new SSDFaceDetector.
- [~SSDFaceDetector](#) () override=default
Destructor of the SSDFaceDetector.

Public Member Functions inherited from [OFIQ_LIB::FaceDetectorInterface](#)

- virtual [~FaceDetectorInterface](#) ()=default
Destroy the Face Detector Interface object.
- `std::vector< OFIQ::BoundingBox > detectFaces` ([OFIQ_LIB::Session](#) &session)
This function detects faces in given image.

Protected Member Functions

- `std::vector< OFIQ::BoundingBox > UpdateFaces` ([OFIQ_LIB::Session](#) &session) override
Implementation of the face detection method.

Private Attributes

- `std::shared_ptr< cv::dnn::Net > dnnNet` {nullptr}
Instance of an opencv dnn::Net.
- double [confidenceThreshold](#)
Confidence threshold used for the face detection. The value is read from the configuration file.
- double [padding](#)
*Add padding around the image (faceImage.width * padding; faceImage.height * padding;)*
- double [minimalRelativeFaceSize](#)
Filter threshold for removing to small face found on the image. This value is read from the configuration file.

7.52.1 Detailed Description

Implementation of a face detector using the SSD face detector CNN.

7.52.2 Constructor & Destructor Documentation

7.52.2.1 SSDFaceDetector()

```
OFIQ_LIB::modules::detectors::SSDFaceDetector::SSDFaceDetector (
    const Configuration & config ) [explicit]
```

Constructor a new SSDFaceDetector.

Parameters

<i>config</i>

7.52.2.2 ~SSDFaceDetector()

```
OFIQ_LIB::modules::detectors::SSDFaceDetector::~~SSDFaceDetector ( ) [override], [default]
```

Destructor of the SSDFaceDetector.

7.52.3 Member Function Documentation**7.52.3.1 UpdateFaces()**

```
std::vector< OFIQ::BoundingBox > OFIQ_LIB::modules::detectors::SSDFaceDetector::UpdateFaces (
    OFIQ_LIB::Session & session ) [override], [protected], [virtual]
```

Implementation of the face detection method.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Returns

std::vector<OFIQ::BoundingBox> Bounding boxes of the detected faces

Implements [OFIQ_LIB::FaceDetectorInterface](#).

7.52.4 Member Data Documentation**7.52.4.1 confidenceThreshold**

```
double OFIQ_LIB::modules::detectors::SSDFaceDetector::confidenceThreshold [private]
```

Confidence threshold used for the face detection. The value is read from the configuration file.

7.52.4.2 dnnNet

```
std::shared_ptr<cv::dnn::Net> OFIQ_LIB::modules::detectors::SSDFaceDetector::dnnNet {nullptr}
[private]
```

Instance of an opencv dnn::Net.

7.52.4.3 minimalRelativeFaceSize

```
double OFIQ_LIB::modules::detectors::SSDFaceDetector::minimalRelativeFaceSize [private]
```

Filter threshold for removing to small face found on the image. This value is read from the configuration file.

7.52.4.4 padding

```
double OFIQ_LIB::modules::detectors::SSDFaceDetector::padding [private]
```

Add padding around the image (facelImage.width * padding; facelImage.height * padding;)

The documentation for this class was generated from the following file:


- [opencv_ssd_face_detector.h](#)

7.53 OFIQ_LIB::modules::measures::UnderExposurePrevention Class Reference

Implementation of the under-exposure prevention measure.

```
#include <UnderExposurePrevention.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::UnderExposurePrevention:



Public Member Functions

- [UnderExposurePrevention](#) (const [Configuration](#) &configuration, [Session](#) &session)
Constructor a new Under Exposure Prevention object.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run the computation of the under-exposure prevention measure.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.53.1 Detailed Description

Implementation of the under-exposure prevention measure.

The representation of a face is considered too dark if it has a high proportion of pixels that have a low luminance value.

7.53.2 Constructor & Destructor Documentation

7.53.2.1 UnderExposurePrevention()

```
OFIQ_LIB::modules::measures::UnderExposurePrevention::UnderExposurePrevention (
    const Configuration & configuration,
    Session & session )
```

Constructor a new Under Exposure Prevention object.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.53.3 Member Function Documentation

7.53.3.1 Execute()

```
void OFIQ_LIB::modules::measures::UnderExposurePrevention::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Run the computation of the under-exposure prevention measure.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

The documentation for this class was generated from the following file:


- [UnderExposurePrevention.h](#)

7.54 OFIQ_LIB::modules::measures::UnifiedQualityScore Class Reference

Implementation of the unified quality measure.

```
#include <UnifiedQualityScore.h>
```

Inheritance diagram for OFIQ_LIB::modules::measures::UnifiedQualityScore:



Public Member Functions

- [UnifiedQualityScore](#) (const [Configuration](#) &configuration, [Session](#) &session)
Construct a new Unified Quality Score object.
- void [Execute](#) ([OFIQ_LIB::Session](#) &session) override
Run the computation on the measure.

Public Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- [Measure](#) (const [Configuration](#) &configuration, const [OFIQ_LIB::Session](#) &, [OFIQ::QualityMeasure](#) measure)
Constructor.
- virtual [~Measure](#) ()=default
Destructor.
- virtual std::string [GetName](#) () const
Returns the name of the measure.
- virtual [OFIQ::QualityMeasure](#) [GetQualityMeasure](#) () const
Returns an enum encoding the measure.
- void [SetQualityMeasure](#) ([OFIQ_LIB::Session](#) &session, [OFIQ::QualityMeasure](#) measure, double rawValue, [OFIQ::QualityMeasureReturnCode](#) code)
Inserts the result of a quality assessment in the session object.

Private Attributes

- [ONNXRuntimeSegmentation m_onnxRuntimeEnv](#)
Instance of the neural network (iResNet50 model M).

Additional Inherited Members

Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- void [AddSigmoid](#) ([OFIQ::QualityMeasure](#) measure, const [SigmoidParameters](#) &defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- void [AddSigmoid](#) (const std::string &key, [SigmoidParameters](#) defaultValues)
Reads sigmoid-function based quality mapping from the configuration.
- double [ExecuteScalarConversion](#) ([OFIQ::QualityMeasure](#) measure, double rawValue)
Maps a native quality score to a quality component value.
- double [ExecuteScalarConversion](#) (const std::string &key, double rawValue)
Maps a native quality score to a quality component value.

Static Protected Member Functions inherited from [OFIQ_LIB::modules::measures::Measure](#)

- static double [Sigmoid](#) (double x, double x0, double w)
Sigmoid function.

Protected Attributes inherited from [OFIQ_LIB::modules::measures::Measure](#)

- const [Configuration](#) & configuration
Reference to the configuration with which the measure constructor has been invoked.

7.54.1 Detailed Description

Implementation of the unified quality measure.

The quality score refers to the requirements in clause 5.4.8 in ISO/IEC 19794-5:2011 frontal image type (relevant for EU-EES implementing decision 2019/329) and in clause 7.7 in ISO/IEC 39794-1 (relevant for UC1 specified in ICAO Document 9303)

7.54.2 Constructor & Destructor Documentation

7.54.2.1 UnifiedQualityScore()

```
OFIQ_LIB::modules::measures::UnifiedQualityScore::UnifiedQualityScore (
    const Configuration & configuration,
    Session & session )
```

Construct a new Unified Quality Score object.

Parameters

<i>configuration</i>	Configuration object from which measure-related configuration is read.
<i>session</i>	Session object containing the original facial image and pre-processing results computed by the OFIQImpl::performPreprocessing() method

7.54.3 Member Function Documentation

7.54.3.1 Execute()

```
void OFIQ_LIB::modules::measures::UnifiedQualityScore::Execute (
    OFIQ_LIB::Session & session ) [override], [virtual]
```

Run the computation on the measure.

The algorithm uses a iResNet50 model M from <https://github.com/IrvingMeng/MagFace> trained on MS1MV2 with MagFace loss without DDP parallelisation. The algorithm takes as input the image I output by the alignment algorithm.

Parameters

<i>session</i>	Session object computed by the OFIQImpl::performPreprocessing() method.
----------------	---

Implements [OFIQ_LIB::modules::measures::Measure](#).

7.54.4 Member Data Documentation

7.54.4.1 m_onnxRuntimeEnv

```
ONNXRuntimeSegmentation OFIQ_LIB::modules::measures::UnifiedQualityScore::m_onnxRuntimeEnv
[private]
```

Instance of the neural network (iResNet50 model M).

The documentation for this class was generated from the following file:

- [UnifiedQualityScore.h](#)

Chapter 8

File Documentation

8.1 mainpage.h File Reference

This header file is for generating the doxygen documentation for OFIQ.

8.1.1 Detailed Description

This header file is for generating the doxygen documentation for OFIQ.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.2 mainpage.h

[Go to the documentation of this file.](#)

```
00001
01147 #pragma once
```

8.3 ofiq_lib.h File Reference

Class describing the interface to the OFIQ.

```
#include <stdint>
#include <string>
#include <vector>
#include <ofiq_structs.h>
```

Classes

- class [OFIQ::Interface](#)
The interface to FACE QA implementation.

Namespaces

- namespace [OFIQ](#)
Namespace for OFIQ API.

Macros

- `#define` [OFIQ_EXPORT](#)

8.3.1 Detailed Description

Class describing the interface to the OFIQ.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.3.2 Macro Definition Documentation

8.3.2.1 OFIQ_EXPORT

```
#define OFIQ_EXPORT
```

8.4 ofiq_lib.h

[Go to the documentation of this file.](#)

```
00001
00027 #ifndef OFIQ_LIB_H
00028 #define OFIQ_LIB_H
00029
00030 #include <cstdint>
00031 #include <string>
00032 #include <vector>
00033
00034 #include <ofiq_structs.h>
00035
00036 #ifdef _WIN32
00037 #   ifdef OFIQ_EXPORTS
00038 #       define OFIQ_EXPORT __declspec(dllexport)
00039 #   else
00040 #       define OFIQ_EXPORT __declspec(dllimport)
00041 #   endif
00042 #else
00043 #   define OFIQ_EXPORT
00044 #endif
00045
00049 namespace OFIQ
00050 {
00051
00059     class Interface
00060     {
00061     public:
00066         virtual ~Interface() = default;
00067
00080         virtual OFIQ::ReturnStatus
00081             initialize(const std::string& configDir, const std::string& configFileName) = 0;
00082
00095         virtual OFIQ::ReturnStatus scalarQuality(const OFIQ::Image& face, double& quality) = 0;
00096
00115         virtual OFIQ::ReturnStatus vectorQuality(
00116             const OFIQ::Image& image, OFIQ::FaceImageQualityAssessment& assessments) = 0;
00117
00133         OFIQ_EXPORT static std::shared_ptr<Interface> getImplementation();
00134     };
00135 }
00136
00137 #endif /* OFIQ_LIB_H */
```

8.5 ofiq_lib_impl.h File Reference

Implementation of the OFIQ_LIB.

```
#include "Configuration.h"
#include "Executor.h"
#include "ofiq_lib.h"
#include "NeuronalNetworkContainer.h"
```

Classes

- class [OFIQ_LIB::OFIQImpl](#)
Implementation of the OFIQ_LIB.

Namespaces

- namespace `OFIQ_LIB`
Namespace for OFIQ implementations.

8.5.1 Detailed Description

Implementation of the OFIQ_LIB.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.6 ofiq_lib_impl.h

[Go to the documentation of this file.](#)

```
00001
00027 #ifndef OFIQ_LIB_IMPL_H
00028 #define OFIQ_LIB_IMPL_H
00029
00030 #include "Configuration.h"
00031 #include "Executor.h"
00032 #include "ofiq_lib.h"
00033 #include "NeuronalNetworkContainer.h"
00034
00038 namespace OFIQ_LIB
00039 {
00044     class OFIQImpl : public OFIQ::Interface
00045     {
00046     public:
00051         OFIQImpl();
00052
00057         ~OFIQImpl() override = default;
00058
00066         OFIQ::ReturnStatus
00067             initialize(const std::string& configDir, const std::string& configValue) override;
00068
00069         OFIQ::ReturnStatus scalarQuality(const OFIQ::Image& face, double& quality) override;
00078
00079         OFIQ::ReturnStatus vectorQuality(
00088             const OFIQ::Image& image, OFIQ::FaceImageQualityAssessment& assessments) override;
00089
```



```

00090
00091     private:
00096         std::unique_ptr<OFIQ_LIB::modules::measures::Executor> m_executorPtr;
00097
00102         OFIQ::FaceImageQualityAssessment dummyAssesment;
00103
00108         OFIQ::Image dummyImage;
00109
00114         OFIQ_LIB::Session m_emptySession;
00115
00116
00121         std::unique_ptr<Configuration> config;
00122
00127         std::unique_ptr<NeuronalNetworkContainer> networks;
00128
00137         std::unique_ptr<OFIQ_LIB::modules::measures::Executor> CreateExecutor(Session& session);
00138
00139
00144         void CreateNetworks();
00145
00153         void performPreprocessing(Session& session);
00154
00162         void alignFaceImage(Session& session);
00163     };
00164 }
00165
00166 #endif /* OFIQ_LIB_IMPL_H */

```

8.7 ofiq_structs.h File Reference

PRovides several helper classes, enums and functions used in the OFIQ framework.

```

#include <cstdint>
#include <iostream>
#include <map>
#include <memory>
#include <string>
#include <utility>
#include <vector>

```

Classes

- struct [OFIQ::Image](#)
Struct representing a single image.
- struct [OFIQ::ReturnStatus](#)
A structure to contain information about a failure by the software under test.
- struct [OFIQ::QualityMeasureResult](#)
Data structure to handle the results of a quality measure.
- struct [OFIQ::BoundingBox](#)
Data structure for describing bounding boxes, e.g. the face region of the faces found by a face detector.
- struct [OFIQ::LandmarkPoint](#)
Data structure to describe the x and y coordinate of a landmark.
- struct [OFIQ::FaceLandmarks](#)
Data structure for storing facial landmarks.
- struct [OFIQ::FaceImageQualityAssessment](#)
Data structure storing the results of the different measurement computations.

Namespaces

- namespace [OFIQ](#)
Namespace for OFIQ API.

Typedefs

- using `OFIQ::QualityAssessments` = `std::map<QualityMeasure, QualityMeasureResult>`
Data structure that stores key-value pairs, with each entry representing a quality element and its value.
- using `OFIQ::Landmarks` = `std::vector<LandmarkPoint>`
container for a collection of landmarks, e.g. belonging to all the landmarks detected on a face image.

Enumerations

- enum class `OFIQ::ReturnCode` {
`OFIQ::Success` = 0 , `OFIQ::ImageReadingError` , `OFIQ::ImageWritingError` , `OFIQ::MissingConfigParamError` ,
`OFIQ::UnknownConfigParamError` , `OFIQ::FaceDetectionError` , `OFIQ::FaceLandmarkExtractionError` ,
`OFIQ::FaceOcclusionSegmentationError` ,
`OFIQ::FaceParsingError` , `OFIQ::UnknownError` , `OFIQ::QualityAssessmentError` , `OFIQ::NotImplemented` }
Return codes for functions specified in this API.
- enum class `OFIQ::QualityMeasure` {
`OFIQ::UnifiedQualityScore` = 0x41 , `OFIQ::BackgroundUniformity` = 0x42 , `OFIQ::IlluminationUniformity` = 0x43 ,
`OFIQ::Luminance` = -0x44 ,
`OFIQ::LuminanceMean` = 0x44 , `OFIQ::LuminanceVariance` = 0x45 , `OFIQ::UnderExposurePrevention` = 0x46 ,
`OFIQ::OverExposurePrevention` = 0x47 ,
`OFIQ::DynamicRange` = 0x48 , `OFIQ::Sharpness` = 0x49 , `OFIQ::CompressionArtifacts` = 0x4a ,
`OFIQ::NaturalColour` = 0x4b ,
`OFIQ::SingleFacePresent` = 0x4c , `OFIQ::EyesOpen` = 0x4d , `OFIQ::MouthClosed` = 0x4e , `OFIQ::EyesVisible` = 0x4f ,
`OFIQ::MouthOcclusionPrevention` = 0x50 , `OFIQ::FaceOcclusionPrevention` = 0x51 , `OFIQ::InterEyeDistance` = 0x52 ,
`OFIQ::HeadSize` = 0x53 ,
`OFIQ::CropOfTheFaceImage` = -0x54 , `OFIQ::LeftwardCropOfTheFaceImage` = 0x54 , `OFIQ::RightwardCropOfTheFaceImage` = 0x55 ,
`OFIQ::DownwardCropOfTheFaceImage` = 0x56 ,
`OFIQ::UpwardCropOfTheFaceImage` = 0x57 , `OFIQ::HeadPose` = -0x58 , `OFIQ::HeadPoseYaw` = 0x58 ,
`OFIQ::HeadPosePitch` = 0x59 ,
`OFIQ::HeadPoseRoll` = 0x5a , `OFIQ::ExpressionNeutrality` = 0x5b , `OFIQ::NoHeadCoverings` = 0x5c ,
`OFIQ::NotSet` = -1 }
Enums presenting the measure labels.
- enum class `OFIQ::QualityMeasureReturnCode` { `OFIQ::Success` = 0 , `OFIQ::FailureToAssess` , `OFIQ::NotInitialized` }
Return codes for QualityMeasureResult.
- enum class `OFIQ::FaceDetectorType` { `OFIQ::OPENCVSSD` , `OFIQ::NotSet` }
Enum describing the different face detector implementations.
- enum class `OFIQ::LandmarkType` { `OFIQ::LM_98` , `OFIQ::NotSet` }
Enum describing the different implementations of landmarks.

Functions

- `std::ostream & OFIQ::operator<<` (`std::ostream &s`, const `ReturnCode` &rc)

8.7.1 Detailed Description

PRovides several helper classes, enums and functions used in the OFIQ framework.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.8 ofiq_structs.h

[Go to the documentation of this file.](#)

```
00001
00027 #ifndef OFIQ_STRUCTS_H
00028 #define OFIQ_STRUCTS_H
00029
00030 #include <stdint>
00031 #include <iostream>
00032 #include <map>
00033 #include <memory>
00034 #include <string>
00035 #include <utility>
00036 #include <vector>
00037
00041 namespace OFIQ
00042 {
00047     struct Image
00048     {
00049
00051         uint16_t width{ 0 };
00053         uint16_t height{ 0 };
00055         uint8_t depth{ 24 };
00060         std::shared_ptr<uint8_t> data;
00061
00065         Image() = default;
00066
00075         Image(uint16_t width, uint16_t height, uint8_t depth, std::shared_ptr<uint8_t>& data)
00076             : width{width},
00077               height{height},
00078               depth{depth},
00079               data{data}
00080         {
00081         }
00082
00084         size_t size() const { return (static_cast<size_t>(width) * height * (depth / 8)); }
00085     };
00086
00087
00092     enum class ReturnCode
00093     {
00095         Success = 0,
00097         ImageReadingError,
00099         ImageWritingError,
00101         MissingConfigParamError,
00103         UnknownConfigParamError,
00105         FaceDetectionError,
00107         FaceLandmarkExtractionError,
```

```

00109     FaceOcclusionSegmentationError,
00111     FaceParsingError,
00113     UnknownError,
00115     QualityAssessmentError,
00117     NotImplemented
00118 };
00119
00121 inline std::ostream& operator<<(std::ostream& s, const ReturnCode& rc)
00122 {
00123     switch (rc)
00124     {
00125     case ReturnCode::Success:
00126         return (s << "Success");
00127     case ReturnCode::UnknownError:
00128         return (s << "Unknown Error");
00129     case ReturnCode::QualityAssessmentError:
00130         return (s << "Failure to generate a quality score on the input image");
00131     case ReturnCode::NotImplemented:
00132         return (s << "Function is not implemented");
00133     default:
00134         return (s << "Undefined error");
00135     }
00136 }
00137
00150 struct ReturnStatus
00151 {
00153     ReturnCode code{ ReturnCode::UnknownError };
00155     std::string info;
00156
00161     ReturnStatus() = default;
00162
00172     ReturnStatus(const ReturnCode code, const std::string& info = "")
00173         : code{code},
00174           info{info}
00175     {
00176     }
00177 };
00178
00181 enum class QualityMeasure
00182 {
00184     UnifiedQualityScore = 0x41,
00186     BackgroundUniformity = 0x42,
00188     IlluminationUniformity = 0x43,
00190     Luminance = -0x44 ,
00192     LuminanceMean = 0x44,
00194     LuminanceVariance = 0x45,
00196     UnderExposurePrevention = 0x46,
00198     OverExposurePrevention = 0x47,
00200     DynamicRange = 0x48,
00202     Sharpness = 0x49,
00204     CompressionArtifacts = 0x4a ,
00206     NaturalColour = 0x4b,
00208     SingleFacePresent = 0x4c ,
00210     EyesOpen = 0x4d ,
00212     MouthClosed = 0x4e,
00214     EyesVisible = 0x4f,
00216     MouthOcclusionPrevention = 0x50,
00218     FaceOcclusionPrevention = 0x51,
00220     InterEyeDistance = 0x52,
00222     HeadSize = 0x53,
00224     CropOfTheFaceImage = -0x54,
00226     LeftwardCropOfTheFaceImage = 0x54,
00228     RightwardCropOfTheFaceImage = 0x55,
00230     DownwardCropOfTheFaceImage = 0x56,
00232     UpwardCropOfTheFaceImage = 0x57,
00234     HeadPose = -0x58,
00236     HeadPoseYaw = 0x58,
00238     HeadPosePitch = 0x59,
00240     HeadPoseRoll = 0x5a,
00242     ExpressionNeutrality = 0x5b,
00244     NoHeadCoverings = 0x5c,
00246     NotSet = -1
00247 };
00248
00253 enum class QualityMeasureReturnCode
00254 {
00256     Success = 0,
00258     FailureToAssess,
00260     NotInitialized
00261 };
00262
00267 struct QualityMeasureResult
00268 {
00270     double rawScore{ -1 };
00274     double scalar{ -1 };
00276     QualityMeasureReturnCode code{ QualityMeasureReturnCode::NotInitialized };
00277

```

```

00282     QualityMeasureResult() = default;
00283
00291     QualityMeasureResult(double rawScore, double scalar = -1, QualityMeasureReturnCode code =
QualityMeasureReturnCode::NotInitialized)
00292         : rawScore{rawScore},
00293           scalar{scalar},
00294           code{code}
00295     {
00296     }
00297 };
00298
00304 using QualityAssessments = std::map<QualityMeasure, QualityMeasureResult>;
00305
00310 enum class FaceDetectorType
00311 {
00313     OPENCVSSD,
00315     NotSet
00316 };
00317
00318 struct BoundingBox
00324 {
00325     int16_t xleft{ -1 };
00328     int16_t ytop{ -1 };
00331     int16_t width{ -1 };
00333     int16_t height{ -1 };
00335
00336     FaceDetectorType faceDetector = FaceDetectorType::NotSet;
00338
00339     BoundingBox() = default;
00344
00345     BoundingBox(int16_t xleft, int16_t ytop, int16_t width, int16_t height, FaceDetectorType
i_faceDetector)
00356         : xleft{xleft},
00357           ytop{ytop},
00358           width{width},
00359           height{height},
00360           faceDetector(i_faceDetector)
00361     {
00362     }
00363 };
00364
00369 struct LandmarkPoint
00370 {
00375     int16_t x{ -1 };
00380     int16_t y{-1 };
00381
00386     LandmarkPoint() = default;
00387
00394     LandmarkPoint(int16_t i_x, int16_t i_y)
00395         : x{i_x},
00396           y{i_y}
00397     {
00398     }
00399 };
00400
00405 using Landmarks = std::vector<LandmarkPoint>;
00406
00411 enum class LandmarkType
00412 {
00414     LM_98,
00416     NotSet
00417 };
00418
00419
00420
00425 struct FaceLandmarks
00426 {
00428     LandmarkType type{ LandmarkType::NotSet };
00430     Landmarks landmarks;
00431
00433     FaceLandmarks() = default;
00434 };
00435
00440 struct FaceImageQualityAssessment
00441 {
00442
00447     QualityAssessments qAssessments;
00448
00453     BoundingBox boundingBox;
00454
00459     FaceImageQualityAssessment() = default;
00460
00467     FaceImageQualityAssessment(
00468         const QualityAssessments& qAssessments, const BoundingBox& boundingBox)
00469         : qAssessments{qAssessments},
00470           boundingBox{boundingBox}

```

```
00471     {
00472     }
00473     };
00474
00475 }
00476
00477 #endif /* OFIQ_STRUCTS_H */
```

8.9 AllDetectors.h File Reference

Provides the include statements to all classes derived from [FaceDetectorInterface](#).

```
#include "opencv_ssd_face_detector.h"
```

8.9.1 Detailed Description

Provides the include statements to all classes derived from [FaceDetectorInterface](#).

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.10 AllDetectors.h

[Go to the documentation of this file.](#)

```
00001
00028 #include "opencv_ssd_face_detector.h"
```

8.11 detectors.h File Reference

Provides the interface class to the face detector implementations.

```
#include "ofiq_lib.h"  
#include "Session.h"
```

Classes

- class [OFIQ_LIB::FaceDetectorInterface](#)
Provides the interface class to the face detector implementations.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

8.11.1 Detailed Description

Provides the interface class to the face detector implementations.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.12 detectors.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "ofiq_lib.h"
00031 #include "Session.h"
00032
00036 namespace OFIQ_LIB
00037 {
00038
00043     class FaceDetectorInterface
00044     {
00045     public:
00050         virtual ~FaceDetectorInterface() = default;
00051
00058         std::vector<OFIQ::BoundingBox> detectFaces (OFIQ_LIB::Session& session);
00059
00060     protected:
00068         virtual std::vector<OFIQ::BoundingBox> UpdateFaces (OFIQ_LIB::Session& session) = 0;
00069     };
00070 }
```

8.13 opencv_ssd_face_detector.h File Reference

Implementation of a face detector using the SSD face detector CNN.

```
#include "Configuration.h"
#include "detectors.h"
#include <opencv2/dnn.hpp>
```

Classes

- class [OFIQ_LIB::modules::detectors::SSDFaceDetector](#)
Implementation of a face detector using the SSD face detector CNN.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::detectors](#)
Provides face detector implementations.

8.13.1 Detailed Description

Implementation of a face detector using the SSD face detector CNN.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.14 opencv_ssd_face_detector.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "Configuration.h"
00030 #include "detectors.h"
00031 #include <opencv2/dnn.hpp>
00032
00033
00037 namespace OFIQ_LIB::modules::detectors
00038 {
00039
00043     class SSDFaceDetector : public OFIQ_LIB::FaceDetectorInterface
00044     {
00045     public:
00051         explicit SSDFaceDetector(const Configuration& config);
00052
00057         ~SSDFaceDetector() override = default;
00058
00059     protected:
00067         std::vector<OFIQ::BoundingBox> UpdateFaces(OFIQ_LIB::Session& session) override;
00068
00069
00070     private:
00075         std::shared_ptr<cv::dnn::Net> dnnNet{nullptr};
00076
00081         double confidenceThreshold;
00082
00087         double padding;
00088
00093         double minimalRelativeFaceSize;
00094     };
00095 }

```

8.15 adnet_FaceMap.h File Reference

Provides definitions of landmark indices to access specific parts of ADNet landmarks.

```

#include "FaceParts.h"
#include <array>
#include <map>
#include <vector>

```

Namespaces

- namespace `OFIQ_LIB`
Namespace for OFIQ implementations.
- namespace `OFIQ_LIB::modules`
- namespace `OFIQ_LIB::modules::landmarks`
Provides implementations of a landmark extractors.
- namespace `OFIQ_LIB::modules::landmarks::adnet`
Namespace for ADNet-specific landmarks.

Variables

- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::leftEye` {60,61,62,63,64,65,66,67}
Landmark indices (ADNet) of the left eye.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::rightEye` {68,69,70,71,72,73,74,75}
Landmark indices (ADNet) of the right eye.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::leftEyeCorners` {60,64}
Landmark indices (ADNet) of the left eyes' corners.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::rightEyeCorners` {68,72}
Landmark indices (ADNet) of the right eyes' corners.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::nosetip` {54}
Landmark index (ADNet) of the nose tip.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::mouthOuter` {76,77,78,79,80,81,82,83,84,85,86,87}
Landmark indices (ADNet) on the mouth's outer contour.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::mouthInner` {88,89,90,91,92,93,94,95}
Landmark indices (ADNet) on the mouth's inner lip borders.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::contour` {0,1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,19,20,21,22}
Landmark indices (ADNet) of the face contour.
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::forehead` {}
Landmark indices (ADNet) of the forehead (empty for ADNet).
- const `LandmarkIds OFIQ_LIB::modules::landmarks::adnet::chin` {16}
Landmark index (ADNet) of the chin.
- const `landmarks::FaceMap OFIQ_LIB::modules::landmarks::adnet::FaceMap`
ADNets face map definition.
- const `LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsLeftEye`
Pair indices of landmarks (ADNet) for the left eye.
- const `LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsRightEye`
Landmark index pairs (ADNet) of landmarks for the right eye.
- const `LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsInnerLip`
Landmark index pairs (ADNet) of inner lip pairs.
- const `LandmarkIdPairs OFIQ_LIB::modules::landmarks::adnet::pairsMouthCenter`
Landmark index pair (ADNet) of the inner mouth (lips) center.
- const `landmarks::FacePairMap OFIQ_LIB::modules::landmarks::adnet::FacePairMap`
ADNets face pair map definition.

8.15.1 Detailed Description

Provides definitions of landmark indices to access specific parts of ADNet landmarks.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

The definitions provided by this header were taken from <https://arxiv.org/pdf/2109.05721.pdf> Appendix A, Figure 6.

Author

OFIQ development team

8.16 adnet_FaceMap.h

[Go to the documentation of this file.](#)

```
00001
00033 #pragma once
00034
00035 #include "FaceParts.h"
00036 #include <array>
00037 #include <map>
00038 #include <vector>
00039
00043 namespace OFIQ_LIB::modules::landmarks::adnet
00044 {
00049     const LandmarkIds leftEye{60, 61, 62, 63, 64, 65, 66, 67};
00050
00055     const LandmarkIds rightEye{68, 69, 70, 71, 72, 73, 74, 75};
00056
00060     const LandmarkIds leftEyeCorners{60, 64};
00061
00065     const LandmarkIds rightEyeCorners{68, 72};
00066
00070     const LandmarkIds nosetip{54};
00071
00075     const LandmarkIds mouthOuter{76, 77, 78, 79, 80, 81, 82, 83, 84, 85, 86, 87};
00076
00080     const LandmarkIds mouthInner{88, 89, 90, 91, 92, 93, 94, 95};
00081
00085     const LandmarkIds
00086     contour{0, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27, 28, 29, 30, 31, 32};
00086
00090     const LandmarkIds forehead{};
00091
00095     const LandmarkIds chin{16};
00096
00100     const landmarks::FaceMap FaceMap{
```

```

00101     {FaceParts::LEFT_EYE,      leftEye      },
00102     {FaceParts::RIGHT_EYE,     rightEye     },
00103     {FaceParts::LEFT_EYE_CORNERS, leftEyeCorners},
00104     {FaceParts::RIGHT_EYE_CORNERS, rightEyeCorners},
00105     {FaceParts::MOUTH_OUTER,   mouthOuter   },
00106     {FaceParts::MOUTH_INNER,   mouthInner   },
00107     {FaceParts::FACE_CONTOUR,   contour     },
00108     {FaceParts::CHIN,          chin        },
00109     {FaceParts::NOSETIP,       nosetip     },
00110     {FaceParts::FOREHEAD,      forehead    }
00111 };
00112
00117     const LandmarkIdPairs pairsLeftEye{
00118         {61, 67},
00119         {62, 66},
00120         {63, 65}
00121     };
00122
00127     const LandmarkIdPairs pairsRightEye{
00128         {69, 75},
00129         {70, 74},
00130         {71, 73}
00131     };
00132
00137     const LandmarkIdPairs pairsInnerLip{
00138         {89, 95},
00139         {90, 94},
00140         {91, 93}
00141     };
00142
00147     const LandmarkIdPairs pairsMouthCenter{
00148         {90, 94}
00149     };
00150
00154     const landmarks::FacePairMap FacePairMap{
00155         {FaceParts::LEFT_EYE,   pairsLeftEye   },
00156         {FaceParts::RIGHT_EYE,  pairsRightEye  },
00157         {FaceParts::MOUTH_INNER, pairsInnerLip   },
00158         {FaceParts::MOUTH_CENTER, pairsMouthCenter}
00159     };
00160 }

```

8.17 adnet_landmarks.h File Reference

Provides the [ADNetFaceLandmarkExtractor](#) class.

```

#include <memory>
#include "Configuration.h"
#include "detectors.h"
#include "landmarks.h"

```

Classes

- class [OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor](#)
Class implementing the [FaceLandmarkExtractorInterface](#) interface.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::landmarks](#)
Provides implementations of a landmark extractors.

8.17.1 Detailed Description

Provides the [ADNetFaceLandmarkExtractor](#) class.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.18 adnet_landmarks.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include <memory>
00031 #include "Configuration.h"
00032 #include "detectors.h"
00033 #include "landmarks.h"
00034
00038 namespace OFIQ_LIB::modules::landmarks
00039 {
00040
00042     class ADNetFaceLandmarkExtractorImpl;
00043
00049     class ADNetFaceLandmarkExtractor : public FaceLandmarkExtractorInterface
00050     {
00051     public:
00056         explicit ADNetFaceLandmarkExtractor(const Configuration& config);
00057
00061         ~ADNetFaceLandmarkExtractor() override;
00062
00063     protected:
00071         OFIQ::FaceLandmarks updateLandmarks(OFIQ_LIB::Session& session) override;
00072
00073     #ifdef OFIQ_SINGLE_FACE_PRESENT_WITH_TMTRIC
00087         std::vector<OFIQ::FaceLandmarks> updateLandmarksAllFaces
00088         (OFIQ_LIB::Session& session, const std::vector<OFIQ::BoundingBox>& faces) override;
00089     #endif
00090
00091     private:
00092
00096         std::unique_ptr<ADNetFaceLandmarkExtractorImpl> landmarkExtractor;
00097     };
00098 }
```

8.19 AllLandmarks.h File Reference

Provides the include statements to all classes derived from [FaceLandmarkExtractorInterface](#).

```
#include "adnet_landmarks.h"
```

8.19.1 Detailed Description

Provides the include statements to all classes derived from [FaceLandmarkExtractorInterface](#).

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.20 AllLandmarks.h

[Go to the documentation of this file.](#)

```
00001  
00029 #include "adnet_landmarks.h"
```

8.21 FaceMeasures.h File Reference

Provides a class implementing two luminance measures.

```
#include "ofiq_lib.h"  
#include "PartExtractor.h"  
#include <opencv2/opencv.hpp>
```

Classes

- class [OFIQ_LIB::modules::landmarks::FaceMeasures](#)
Provides static functions doing computations with landmarks.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::landmarks](#)
Provides implementations of a landmark extractors.

8.21.1 Detailed Description

Provides a class implementing two luminance measures.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.22 FaceMeasures.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "PartExtractor.h"
00031 #include <opencv2/opencv.hpp>
00032
00036 namespace OFIQ_LIB::modules::landmarks
00037 {
00041     class FaceMeasures
00042     {
00043     public:
00047         FaceMeasures() = delete;
00048
00066         static double InterEyeDistance(const OFIQ::FaceLandmarks& faceLandmarks, double yaw);
00067
00078         static cv::Mat GetFaceMask
00079         (const OFIQ::FaceLandmarks& faceLandmarks, const int height, const int width,
00080          const float alpha = 0);
00081
00088         static double GetDistance(const OFIQ::LandmarkPoint& a, const OFIQ::LandmarkPoint& b);
00089
00096         static double GetDistance(const LandmarkPair& pair)
00097         {
00098             return GetDistance(pair.Lower, pair.Upper);
00099         }
00100
00106         static OFIQ::LandmarkPoint GetMiddle(const OFIQ::Landmarks& landmarks);
00107
00113         static OFIQ::LandmarkPoint GetMiddle(const LandmarkPair& pair)
00114         {
00115             return GetMiddle(OFIQ::Landmarks{pair.Lower, pair.Upper});
00116         }
00117
00125         static OFIQ::LandmarkPoint GetMiddle(const std::vector<LandmarkPair>& pairs)
00126         {
00127             std::vector<OFIQ::LandmarkPoint> points;
00128             for (auto pair : pairs)
00129             {
00130                 points.push_back(GetMiddle(pair));
00131             }
00132             return GetMiddle(points);
00133         }
00134
00147         static double GetMaxPairDistance
00148         (const OFIQ::FaceLandmarks& landmarks,
00149          landmarks::FaceParts facePart);
00150     };
00151 }

```

8.23 FaceParts.h File Reference

Provides several helper classes, enums and functions used in the OFIQ framework.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::landmarks](#)
Provides implementations of a landmark extractors.

Typedefs

- using `OFIQ_LIB::modules::landmarks::LandmarkId` = int
Type definition of a landmark index.
- using `OFIQ_LIB::modules::landmarks::LandmarkIds` = `std::vector<LandmarkId>`
Type definition of a list of landmark indices.
- using `OFIQ_LIB::modules::landmarks::FaceMap` = `std::map<FaceParts, LandmarkIds>`
Type definition of a face map to access landmark indices for a queried face part.
- using `OFIQ_LIB::modules::landmarks::LandmarkIdPair` = `std::array<LandmarkId, 2>`
Type definition for a pair of landmark index.
- using `OFIQ_LIB::modules::landmarks::LandmarkIdPairs` = `std::vector<LandmarkIdPair>`
Type definition for a list of landmark index pairs.
- using `OFIQ_LIB::modules::landmarks::FacePairMap` = `std::map<FaceParts, LandmarkIdPairs>`
Structure defining pairs of landmark indices.

Enumerations

- enum class `OFIQ_LIB::modules::landmarks::FaceParts` {
`OFIQ_LIB::modules::landmarks::LEFT_EYE`, `OFIQ_LIB::modules::landmarks::RIGHT_EYE`, `OFIQ_LIB::modules::landmarks::RIGHT_EYE_CORNERS`,
`OFIQ_LIB::modules::landmarks::MOUTH_OUTER`, `OFIQ_LIB::modules::landmarks::MOUTH_INNER`,
`OFIQ_LIB::modules::landmarks::FACE_CONTOUR`, `OFIQ_LIB::modules::landmarks::MOUTH_CENTER`
, `OFIQ_LIB::modules::landmarks::CHIN`, `OFIQ_LIB::modules::landmarks::NOSETIP`, `OFIQ_LIB::modules::landmarks::FOREHEAD`
}
- Enumeration of facial landmark parts.*

8.23.1 Detailed Description

PROvides several helper classes, enums and functions used in the OFIQ framework.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.24 FaceParts.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00033 namespace OFIQ_LIB::modules::landmarks
00034 {
00038     enum class FaceParts
00039     {
00041         LEFT_EYE,
00043         RIGHT_EYE,
00045         LEFT_EYE_CORNERS,
00047         RIGHT_EYE_CORNERS,
00049         MOUTH_OUTER,
00051         MOUTH_INNER,
00053         FACE_CONTOUR,
00055         MOUTH_CENTER,
00057         CHIN,
00059         NOSETIP,
00061         FOREHEAD
00062     };
00063
00067     using LandmarkId = int;
00068
00072     using LandmarkIds = std::vector<LandmarkId>;
00073
00078     using FaceMap = std::map<FaceParts, LandmarkIds>;
00079
00083     using LandmarkIdPair = std::array<LandmarkId, 2>;
00084
00088     using LandmarkIdPairs = std::vector<LandmarkIdPair>;
00089
00093     using FacePairMap = std::map<FaceParts, LandmarkIdPairs>;
00094 }
```

8.25 landmarks.h File Reference

Provides the base class for the implementation of face landmark extractors.

```
#include "ofiq_lib.h"
#include "Session.h"
```

Classes

- class [OFIQ_LIB::FaceLandmarkExtractorInterface](#)
Implements the base class for the face landmark extractors.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

8.25.1 Detailed Description

Provides the base class for the implementation of face landmark extractors.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.26 landmarks.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "Session.h"
00031
00035 namespace OFIQ_LIB
00036 {
00041     class FaceLandmarkExtractorInterface
00042     {
00043     public:
00048         virtual ~FaceLandmarkExtractorInterface() = default;
00049
00056         OFIQ::FaceLandmarks extractLandmarks(OFIQ_LIB::Session& session);
00057 #ifndef OFIQ_SINGLE_FACE_PRESENT_WITH_TMETRIC //deprecated but required by DIS of ISO/IEC 29794-5
00058         std::vector<OFIQ::FaceLandmarks> extractLandmarksAllFaces(OFIQ_LIB::Session& session, const
std::vector<OFIQ::BoundingBox>& faces );
00059 #endif
00060
00061     protected:
00068         virtual OFIQ::FaceLandmarks updateLandmarks(OFIQ_LIB::Session& session) = 0;
00069 #ifndef OFIQ_SINGLE_FACE_PRESENT_WITH_TMETRIC //deprecated but required by DIS of ISO/IEC 29794-5
00070         virtual std::vector<OFIQ::FaceLandmarks> updateLandmarksAllFaces (
00071             OFIQ_LIB::Session& session, const std::vector<OFIQ::BoundingBox>& faces) = 0;
00072 #endif
00073     };
00074 }
```

8.27 PartExtractor.h File Reference

Provides helper class for face landmark handling.

```
#include "ofiq_lib.h"
#include "FaceParts.h"
```

Classes

- struct [OFIQ_LIB::modules::landmarks::LandmarkPair](#)
Data container for storing pairs of landmarks.
- class [OFIQ_LIB::modules::landmarks::PartExtractor](#)
Class that provides helper methods for the administration of landmarks.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::landmarks](#)
Provides implementations of a landmark extractors.

8.27.1 Detailed Description

Provides helper class for face landmark handling.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.28 PartExtractor.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "FaceParts.h"
00031
00035 namespace OFIQ_LIB::modules::landmarks
00036 {
00037
00042     enum class FaceParts;
00043
00048     struct LandmarkPair
00049     {
00054         OFIQ::LandmarkPoint Upper;
00055
00060         OFIQ::LandmarkPoint Lower;
00061
00068         LandmarkPair(OFIQ::LandmarkPoint upper, OFIQ::LandmarkPoint lower) : Upper{upper},
Lower{lower}
00069     {
00070     }
00071     };
00072
00077     class PartExtractor
00078     {
00079     public:
00088         static OFIQ::Landmarks getFacePart(const OFIQ::FaceLandmarks& faceLandmarks, FaceParts part);
00089
00098         static std::vector<LandmarkPair> getPairsForPart(const OFIQ::FaceLandmarks& faceLandmarks,
FaceParts part);
00099     };
00100 }

```

8.29 AllMeasures.h File Reference

Provides all classes derived from the [OFIQ_LIB::modules::measures::Measure](#) class.

```

#include "BackgroundUniformity.h"
#include "CompressionArtifacts.h"
#include "CropOfTheFaceImage.h"
#include "DynamicRange.h"
#include "ExpressionNeutrality.h"
#include "EyesOpen.h"
#include "EyesVisible.h"
#include "FaceOcclusionPrevention.h"
#include "FaceOcclusionSegmentation.h"
#include "FaceParsing.h"
#include "HeadPose.h"
#include "HeadSize.h"
#include "IlluminationUniformity.h"
#include "InterEyeDistance.h"
#include "Luminance.h"
#include "MouthClosed.h"
#include "MouthOcclusionPrevention.h"
#include "NaturalColour.h"
#include "NoHeadCoverings.h"
#include "OverExposurePrevention.h"
#include "Sharpness.h"
#include "SingleFacePresent.h"
#include "UnderExposurePrevention.h"
#include "UnifiedQualityScore.h"

```

8.29.1 Detailed Description

Provides all classes derived from the `OFIQ_LIB::modules::measures::Measure` class.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.30 AllMeasures.h

[Go to the documentation of this file.](#)

```
00001
00029 #include "BackgroundUniformity.h"
00030 #include "CompressionArtifacts.h"
00031 #include "CropOfTheFaceImage.h"
00032 #include "DynamicRange.h"
00033 #include "ExpressionNeutrality.h"
00034 #include "EyesOpen.h"
00035 #include "EyesVisible.h"
00036 #include "FaceOcclusionPrevention.h"
00037 #include "FaceOcclusionSegmentation.h"
00038 #include "FaceParsing.h"
00039 #include "HeadPose.h"
00040 #include "HeadSize.h"
00041 #include "IlluminationUniformity.h"
00042 #include "InterEyeDistance.h"
00043 #include "Luminance.h"
00044 #include "MouthClosed.h"
00045 #include "MouthOcclusionPrevention.h"
00046 #include "NaturalColour.h"
00047 #include "NoHeadCoverings.h"
00048 #include "OverExposurePrevention.h"
00049 #include "Sharpness.h"
00050 #include "SingleFacePresent.h"
00051 #include "UnderExposurePrevention.h"
00052 #include "UnifiedQualityScore.h"
```

8.31 BackgroundUniformity.h File Reference

Provides a class implementing the background uniformity measure.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::BackgroundUniformity](#)
Implementation of the background uniformity measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.31.1 Detailed Description

Provides a class implementing the background uniformity measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.32 BackgroundUniformity.h

[Go to the documentation of this file.](#)

```

00001
00028 #pragma once
00029
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00043     class BackgroundUniformity : public Measure
00044     {
00045     public:
00053         BackgroundUniformity(
00054             const Configuration& configuration,
00055             Session& session);
00056
00064         void Execute(OFIQ_LIB::Session & session) override;
00065
00066     private:
00071         uint16_t m_target_height = 292;
00072
00077         uint16_t m_target_width = 354;
00078
00084         uint16_t m_crop_left = 62;
00085
00091         uint16_t m_crop_right = 62;
00092
00098         uint16_t m_crop_top = 0;
00099
00105         uint16_t m_crop_bottom = 210;
00106
00113         uint16_t m_erosion_kernel_size = 4;
00114     };
00115 }

```

8.33 CompressionArtifacts.h File Reference

Provides a class implementing the no compression artifact measure.

```

#include "landmarks.h"
#include "Measure.h"
#include <ONNXRTSegmentation.h>

```

Classes

- class [OFIQ_LIB::modules::measures::CompressionArtifacts](#)
Implementation of the no compression artifacts measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.33.1 Detailed Description

Provides a class implementing the no compression artifact measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.34 CompressionArtifacts.h

[Go to the documentation of this file.](#)

```

00001
00028 #pragma once
00029
00030 #include "landmarks.h"
00031 #include "Measure.h"
00032 #include <ONNXRuntimeSegmentation.h>
00033
00037 namespace OFIQ_LIB::modules::measures
00038 {
00045     class CompressionArtifacts : public Measure
00046     {
00047     public:
00071         CompressionArtifacts(const Configuration& configuration, Session& session);
00072
00081         void Execute(OFIQ_LIB::Session& session) override;
00082
00083     private:
00090         uint16_t m_crop;
00091
00099         uint16_t m_dim;
00100
00104         ONNXRuntimeSegmentation m_onnxRuntimeEnv;
00105     };
00106 }

```

8.35 CropOfTheFacelImage.h File Reference

Provides a class implementing the crop of the face image measure.

```

#include "landmarks.h"
#include "Measure.h"

```

Classes

- class [OFIQ_LIB::modules::measures::CropOfTheFaceImage](#)
Implementation of the crop of the face image measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.35.1 Detailed Description

Provides a class implementing the crop of the face image measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.36 CropOfTheFaceImage.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00042     class CropOfTheFaceImage : public Measure
00043     {
00044     public:
00052         CropOfTheFaceImage(const Configuration& configuration, Session& session);
00053
00060         void Execute(OFIQ_LIB::Session & session) override;
00061     };
00062 }
```

8.37 DynamicRange.h File Reference

Provides a class implementing the dynamic range measure.

```
#include "landmarks.h"  
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::DynamicRange](#)
Implementation of the dynamic range measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.37.1 Detailed Description

Provides a class implementing the dynamic range measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.38 DynamicRange.h

[Go to the documentation of this file.](#)

```

00001
00028 #pragma once
00029
00030 #include "landmarks.h"
00031 #include "Measure.h"
00032
00036 namespace OFIQ_LIB::modules::measures
00037 {
00043     class DynamicRange : public Measure
00044     {
00045     public:
00053         DynamicRange(
00054             const Configuration& configuration,
00055             Session& session);
00056
00062         void Execute(OFIQ_LIB::Session & session) override;
00063     };
00064 }

```

8.39 Executor.h File Reference

This class takes care of the computation of the measures activated.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::Executor](#)
This class takes care of the computation of the measures activated.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

Functions

- void [OFIQ_LIB::modules::measures::log](#) (const std::string_view &msg)
Logging function for writing debug messages to std::cout.

Variables

- static const bool [OFIQ_LIB::modules::measures::execLogActive](#) = false
This variable enables logging to std::cout for debug purposes. By default the logging is switched off.

8.39.1 Detailed Description

This class takes care of the computation of the measures activated.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.40 Executor.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00034 namespace OFIQ_LIB::modules::measures
00035 {
00039     const static bool execLogActive = false;
00040
00046     void log(const std::string_view& msg);
00047
00051     class Executor
00052     {
00053     public:
00059         explicit Executor(std::vector<std::unique_ptr<Measure>> measures)
00060             : measures{std::move(measures)}
00061         {
00062         }
00063
00069         void ExecuteAll(Session & i_currentSession) const;
00070
00075         const std::vector<std::unique_ptr<Measure>& GetMeasures() const { return measures; }
00076
00077     private:
00082         std::vector<std::unique_ptr<Measure>> measures;
00083     };
00084 }

```

8.41 ExpressionNeutrality.h File Reference

Provides a class implementing the expression neutrality measure.

```

#include "landmarks.h"
#include "Measure.h"
#include <ONNXRTSegmentation.h>

```

Classes

- class [OFIQ_LIB::modules::measures::ExpressionNeutrality](#)
Provides a class implementing the expression neutrality measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.41.1 Detailed Description

Provides a class implementing the expression neutrality measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.42 ExpressionNeutrality.h

[Go to the documentation of this file.](#)

```

00001
00028 #pragma once
00029
00030 #include "landmarks.h"
00031 #include "Measure.h"
00032 #include <ONNXRTSegmentation.h>
00033
00037 namespace OFIQ_LIB::modules::measures
00038 {
00047     class ExpressionNeutrality : public Measure
00048     {
00049     public:
00057         ExpressionNeutrality(
00058             const Configuration& configuration, Session& session);
00059
00065         void Execute(OFIQ_LIB::Session& session) override;
00066
00067     private:
00072         ONNXRuntimeSegmentation m_onnxRuntimeEnvCNN1;
00073
00078         ONNXRuntimeSegmentation m_onnxRuntimeEnvCNN2;
00079
00084         std::shared_ptr<cv::ml::Boost> classifier;
00085     };
00086 }

```

8.43 EyesOpen.h File Reference

Provides a class implementing the eyes open measure.

```
#include "landmarks.h"  
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::EyesOpen](#)
Implementation of the eyes open measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.43.1 Detailed Description

Provides a class implementing the eyes open measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.44 EyesOpen.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "landmarks.h"
00031 #include "Measure.h"
00032
00036 namespace OFIQ_LIB::modules::measures
00037 {
00043     class EyesOpen : public Measure
00044     {
00045     public:
00053         EyesOpen(const Configuration& configuration, Session& session);
00054
00063         void Execute(OFIQ_LIB::Session & session) override;
00064     };
00065 }
```

8.45 EyesVisible.h File Reference

Provides a class implementing the eyes visible measure.

```
#include "landmarks.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::EyesVisible](#)
Implementation of the eyes visible measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.45.1 Detailed Description

Provides a class implementing the eyes visible measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.46 EyesVisible.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00043     class EyesVisible : public Measure
00044     {
00045     public:
00053         EyesVisible(const Configuration& configuration, Session& session);
00054
00064         void Execute(OFIQ_LIB::Session & session) override;
00065     };
00066 }
```

8.47 FaceOcclusionPrevention.h File Reference

Provides a class implementing the face occlusion prevention measure.

```
#include "landmarks.h"
#include "Measure.h"
#include <ONNXRTSegmentation.h>
```

Classes

- class [OFIQ_LIB::modules::measures::FaceOcclusionPrevention](#)
Implementation of the face occlusion prevention measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.47.1 Detailed Description

Provides a class implementing the face occlusion prevention measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.48 FaceOcclusionPrevention.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031 #include <ONNXRTSegmentation.h>
00032
00036 namespace OFIQ_LIB::modules::measures
00037 {
00044     class FaceOcclusionPrevention : public Measure
00045     {
00046     public:
00054         FaceOcclusionPrevention(
00055             const Configuration& configuration,
00056             Session& session);
00057
00068         void Execute(OFIQ_LIB::Session & session) override;
00069     };
00070 }
```

8.49 HeadPose.h File Reference

Provides a class implementing head pose measures.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::HeadPose](#)
Implementation of head pose measures.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.49.1 Detailed Description

Provides a class implementing head pose measures.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.50 HeadPose.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00034 namespace OFIQ_LIB::modules::measures
00035 {
00040     class HeadPose : public Measure
00041     {
00042     public:
00050         HeadPose(
00051             const Configuration& configuration,
00052             Session& session);
00053
00061         void Execute(OFIQ_LIB::Session & session) override;
00062     };
00063 }
```

8.51 HeadSize.h File Reference

Provides a class implementing the head size measure.

```
#include "landmarks.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::HeadSize](#)
Implementation of the head size measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.51.1 Detailed Description

Provides a class implementing the head size measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.52 HeadSize.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00042     class HeadSize : public Measure
00043     {
00044     public:
00052         HeadSize(
00053             const Configuration& configuration,
00054             Session& session);
00055
00061         void Execute(OFIQ_LIB::Session & session) override;
00062     };
00063 }
```

8.53 IlluminationUniformity.h File Reference

Provides a class implementing the illumination uniformity measure.

```
#include "landmarks.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::IlluminationUniformity](#)
Implementation of the illumination uniformity measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.53.1 Detailed Description

Provides a class implementing the illumination uniformity measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.54 IlluminationUniformity.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "landmarks.h"
00031 #include "Measure.h"
00032
00036 namespace OFIQ_LIB::modules::measures
00037 {
00044     class IlluminationUniformity : public Measure
00045     {
00046     public:
00054         IlluminationUniformity(const Configuration& configuration, Session& session);
00055
00064         void Execute(OFIQ_LIB::Session & session) override;
00065     };
00066 }
```

8.55 InterEyeDistance.h File Reference

Provides a class implementing the inter-eye distance measure.

```
#include "landmarks.h"  
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::InterEyeDistance](#)
Implementation of the inter-eye distance measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.55.1 Detailed Description

Provides a class implementing the inter-eye distance measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.56 InterEyeDistance.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00043     class InterEyeDistance : public Measure
00044     {
00045     public:
00053         InterEyeDistance(const Configuration& configuration, Session& session);
00054
00063         void Execute(OFIQ_LIB::Session & session) override;
00064     };
00065 }
```

8.57 Luminance.h File Reference

Provides a class implementing two luminance measures.

```
#include "landmarks.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::Luminance](#)
Implementation of two luminance measures.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.57.1 Detailed Description

Provides a class implementing two luminance measures.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.58 Luminance.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00042     class Luminance : public Measure
00043     {
00044     public:
00052         Luminance(const Configuration& configuration, Session& session);
00053
00061         void Execute(OFIQ_LIB::Session & session) override;
00062     };
00063 }
```

8.59 Measure.h File Reference

Provides the base class for all measures implemented in OFIQ.

```
#include "Configuration.h"
#include "ofiq_lib.h"
#include "Session.h"
#include <math.h>
```

Classes

- struct [OFIQ_LIB::modules::measures::SigmoidParameters](#)
Parameters of the sigmoid function based quality mapping.
- class [OFIQ_LIB::modules::measures::Measure](#)
Base class for measures implemented in OFIQ.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.59.1 Detailed Description

Provides the base class for all measures implemented in OFIQ.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.60 Measure.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Configuration.h"
00030 #include "ofiq_lib.h"
00031 #include "Session.h"
00032 #ifndef _WIN32
00033 #   include <math.h>
00034 #endif
00035
00039 namespace OFIQ_LIB::modules::measures
00040 {
00056     struct SigmoidParameters
00057     {
00063         SigmoidParameters() { Reset(); }
00064
00069         double h;
00070
00075         double a;
00076
00081         double s;
00082
```

```

00088     double x0;
00089
00095     double w;
00096
00102     bool round;
00103
00112     void setInverse()
00113     {
00114         a = 1;
00115         s = -1;
00116     }
00117
00121     void Reset()
00122     {
00123         h = 100;
00124         a = 0;
00125         s = 1;
00126         x0 = 4;
00127         w = 0.7;
00128         round = true;
00129     }
00130 };
00131
00135 class Measure
00136 {
00137 public:
00146     Measure(const Configuration& configuration,
00147            const OFIQ_LIB::Session&,
00148            OFIQ::QualityMeasure measure)
00149         : configuration{configuration}, m_measure(measure)
00150     {
00151     }
00152
00162     virtual void Execute(OFIQ_LIB::Session& session) = 0;
00163
00167     virtual ~Measure() = default;
00168
00176     virtual std::string GetName() const;
00177
00182     virtual OFIQ::QualityMeasure GetQualityMeasure() const;
00183
00197     void SetQualityMeasure(OFIQ_LIB::Session& session, OFIQ::QualityMeasure measure, double
rawValue, OFIQ::QualityMeasureReturnCode code);
00198
00199 protected:
0207     static double Sigmoid(double x, double x0, double w)
0208     {
0209         return 1.0 / (1 + exp((x0 - x) / w));
0210     }
0211
0224     void AddSigmoid(OFIQ::QualityMeasure measure, const SigmoidParameters& defaultValues);
0225
0238     void AddSigmoid(const std::string& key, SigmoidParameters defaultValues);
0239
0247     double ExecuteScalarConversion(OFIQ::QualityMeasure measure, double rawValue);
0248
0256     double ExecuteScalarConversion(const std::string& key, double rawValue);
0257
0262     const Configuration& configuration;
0263
0264 private:
0275     static double ScalarConversion(double rawValue, const SigmoidParameters& par)
0276     {
0277         double scalarScore = par.h * (par.a + par.s * Sigmoid(rawValue, par.x0, par.w));
0278         if (par.round)
0279             scalarScore = round(scalarScore);
0280         if (scalarScore < 0.0)
0281         {
0282             scalarScore = 0.0;
0283         }
0284         else if (scalarScore > 100.0)
0285         {
0286             scalarScore = 100.0;
0287         }
0288         return scalarScore;
0289     }
0290
0295     std::map<std::string, SigmoidParameters, std::less<> > sigmoidMap;
0296
0302     static std::string GetMeasureName(OFIQ::QualityMeasure measure);
0303
0311     static std::string ExpandKey(std::string_view rawKey);
0312
0318     OFIQ::QualityMeasure m_measure = OFIQ::QualityMeasure::NotSet;
0319 };
0320 }

```

8.61 MeasureFactory.h File Reference

Provides a class for requesting creation of measure implementations.

```
#include "Configuration.h"
#include "ofiq_lib.h"
#include "Measure.h"
#include "Session.h"
```

Classes

- class [OFIQ_LIB::modules::measures::MeasureFactory](#)
Measure factor class.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.61.1 Detailed Description

Provides a class for requesting creation of measure implementations.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.62 MeasureFactory.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "Configuration.h"
00031 #include "ofiq_lib.h"
00032 #include "Measure.h"
00033 #include "Session.h"
00034
00038 namespace OFIQ_LIB::modules::measures
00039 {
00043     class MeasureFactory
00044     {
00045     public:
00046         // Avoids instantiation from this class
00047         MeasureFactory() = delete;
00048
00063         static std::unique_ptr<Measure> CreateMeasure(
00064             const OFIQ::QualityMeasure measure,
00065             const Configuration& configuration,
00066             OFIQ_LIB::Session& session);
00067     };
00068 }
```

8.63 MouthClosed.h File Reference

Provides a class implementing the mouth closed measure.

```
#include "landmarks.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::MouthClosed](#)

Implementation of the mouth closed measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)

Provides measures implemented in OFIQ.

8.63.1 Detailed Description

Provides a class implementing the mouth closed measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.64 MouthClosed.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00042     class MouthClosed : public Measure
00043     {
00044     public:
00052         MouthClosed(
00053             const Configuration& configuration, Session& session);
00054
00063         void Execute(OFIQ_LIB::Session& session) override;
00064     };
00065 }
```

8.65 MouthOcclusionPrevention.h File Reference

Provides a class implementing the mouth occlusion prevention measure.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::MouthOcclusionPrevention](#)
Implementation of the mouth occlusion prevention measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.65.1 Detailed Description

Provides a class implementing the mouth occlusion prevention measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.66 MouthOcclusionPrevention.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00034 namespace OFIQ_LIB::modules::measures
00035 {
00042     class MouthOcclusionPrevention : public Measure
00043     {
00044     public:
00052         MouthOcclusionPrevention(const Configuration& configuration, Session& session);
00053
00065         void Execute(OFIQ_LIB::Session & session) override;
00066     };
00067 }
```

8.67 NaturalColour.h File Reference

Provides a class implementing the natural colour measure.

```
#include "landmarks.h"  
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::NaturalColour](#)
Implementation of the natural colour measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.67.1 Detailed Description

Provides a class implementing the natural colour measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.68 NaturalColour.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00043     class NaturalColour : public Measure
00044     {
00045     public:
00053         NaturalColour(
00054             const Configuration& configuration,
00055             Session& session);
00056
00065         void Execute(OFIQ_LIB::Session & session) override;
00066
00067     private:
00074         cv::Mat CreateMaskedImage(const OFIQ::FaceLandmarks& landmarks, const cv::Mat& cvImage);
00075
00086         cv::Mat ReduceImageToRegionOfInterest
00087         (const cv::Mat maskedImage,
00088          const cv::Rect& leftRegionOfInterest,
00089          const cv::Rect& rightRegionOfInterest);
00090
00104         double CalculateScore(double meanChannelA, double meanChannelB);
00105     };
00106 }

```

8.69 NoHeadCoverings.h File Reference

Provides a class implementing the no head covering measure.

```

#include "Measure.h"
#include "segmentations.h"

```

Classes

- class [OFIQ_LIB::modules::measures::NoHeadCoverings](#)
Implementation of the no head covering measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.69.1 Detailed Description

Provides a class implementing the no head covering measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.70 NoHeadCoverings.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030 #include "segmentations.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00051     class NoHeadCoverings : public Measure
00052     {
00053     public:
00066         NoHeadCoverings(
00067             const Configuration& configuration,
00068             Session& session);
00069
00086         void Execute(OFIQ_LIB::Session & session) override;
00087
00088     private:
00096         double threshold;
00097     };
00098 }
```

8.71 OverExposurePrevention.h File Reference

Provides a class implementing the background uniformity measure.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::OverExposurePrevention](#)
Implementation of the over-exposure prevention measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.71.1 Detailed Description

Provides a class implementing the background uniformity measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.72 OverExposurePrevention.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00042     class OverExposurePrevention : public Measure
00043     {
00044     public:
00052         OverExposurePrevention(
00053             const Configuration& configuration,
00054             Session& session);
00055
00061         void Execute(OFIQ_LIB::Session & session) override;
00062     };
00063 }
```

8.73 Sharpness.h File Reference

Provides a class implementing the sharpness measure.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::Sharpness](#)
Implementation of the sharpness measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.73.1 Detailed Description

Provides a class implementing the sharpness measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.74 Sharpness.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00034 namespace OFIQ_LIB::modules::measures
00035 {
00043     class Sharpness : public Measure
00044     {
00045     public:
00053         Sharpness(
00054             const Configuration& configuration,
00055             Session& session);
00056
00062         void Execute(OFIQ_LIB::Session & session) override;
00063
00064     private:
00065
00069         std::string modelFile;
00070
00075         std::shared_ptr<cv::ml::RTrees> rtree;
00076
00082         bool useAligned;
00083
00089         double faceRegionAlpha;
00090
00095         int numTrees;
00096
00106         void GetCroppedImages(Session& session, cv::Mat& faceCrop, cv::Mat& maskCrop, bool useAligned,
00107             float faceRegionAlpha);
00116         cv::Mat GetClassifierFocusFeatures(cv::Mat& image, cv::Mat& mask, bool applyBlur);
00117     };
00118 }
```

8.75 SingleFacePresent.h File Reference

Provides a class implementing the single face present measure.

```
#include "detectors.h"
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::SingleFacePresent](#)
Implementation of the single face present measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.75.1 Detailed Description

Provides a class implementing the single face present measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.76 SingleFacePresent.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "detectors.h"
00030 #include "Measure.h"
00031
00035 namespace OFIQ_LIB::modules::measures
00036 {
00041     class SingleFacePresent : public Measure
00042     {
00043     public:
00051         SingleFacePresent (
00052             const Configuration& configuration, Session& session);
00053
00060         void Execute(OFIQ_LIB::Session & session) override;
00061     };
00062 }
```

8.77 UnderExposurePrevention.h File Reference

Provides a class implementing the under-exposure prevention measure.

```
#include "Measure.h"
```

Classes

- class [OFIQ_LIB::modules::measures::UnderExposurePrevention](#)
Implementation of the under-exposure prevention measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.77.1 Detailed Description

Provides a class implementing the under-exposure prevention measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.78 UnderExposurePrevention.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "Measure.h"
00030
00034 namespace OFIQ_LIB::modules::measures
00035 {
00041     class UnderExposurePrevention : public Measure
00042     {
00043     public:
00051         UnderExposurePrevention(
00052             const Configuration& configuration,
00053             Session& session);
00054
00060         void Execute(OFIQ_LIB::Session & session) override;
00061     };
00062 }
```

8.79 UnifiedQualityScore.h File Reference

Provides a class implementing the unified quality measure.

```
#include "landmarks.h"
#include "Measure.h"
#include <opencv2/dnn.hpp>
#include <ONNXRTSegmentation.h>
```

Classes

- class [OFIQ_LIB::modules::measures::UnifiedQualityScore](#)
Implementation of the unified quality measure.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::measures](#)
Provides measures implemented in OFIQ.

8.79.1 Detailed Description

Provides a class implementing the unified quality measure.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.80 UnifiedQualityScore.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "landmarks.h"
00030 #include "Measure.h"
00031 #include <opencv2/dnn.hpp>
00032 #include <ONNXRTSegmentation.h>
00033
00037 namespace OFIQ_LIB::modules::measures
00038 {
00046     class UnifiedQualityScore : public Measure
00047     {
00048     public:
00056         UnifiedQualityScore(
00057             const Configuration& configuration,
00058             Session& session);
00059
00069         void Execute(OFIQ_LIB::Session & session) override;
00070
00071     private:
00076         ONNXRuntimeSegmentation m_onnxRuntimeEnv;
00077     };
00078 }
```

8.81 AllPoseEstimators.h File Reference

```
#include "HeadPose3DDFAV2.h"
```

8.81.1 Detailed Description

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

@briefPProvides the include statements to all classes derived from [PoseEstimatorInterface](#).

Author

OFIQ development team

8.82 AllPoseEstimators.h

[Go to the documentation of this file.](#)

```
00001
00029 #include "HeadPose3DDFAV2.h"
```

8.83 HeadPose3DDFAV2.h File Reference

Provides a class implementing a head pose estimator based on https://github.com/cleardusk/3DDFA_V2.

```
#include "Configuration.h"
#include "poseEstimators.h"
#include <onnxruntime_cxx_api.h>
#include <opencv2/core/mat.hpp>
```

Classes

- class [OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2](#)
Implementation of a head pose estimator.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::poseEstimators](#)
Provides implementation of a head pose estimator.

8.83.1 Detailed Description

Provides a class implementing a head pose estimator based on https://github.com/cleardusk/3DDFA_V2.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.84 HeadPose3DDFAV2.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "Configuration.h"
00030 #include "poseEstimators.h"
00031 #include <onnxruntime_cxx_api.h>
00032 #include <opencv2/core/mat.hpp>
00033
00038 namespace OFIQ_LIB::modules::poseEstimators
00039 {
00044     class HeadPose3DDFAV2 : public PoseEstimatorInterface
00045     {
00046     public:
00053         explicit HeadPose3DDFAV2(const Configuration& config);
00054
00058         ~HeadPose3DDFAV2() override = default;
00059
00060     protected:
00068         void updatePose(OFIQ_LIB::Session& session, EulerAngle& pose) override;
00069
00070     private:
00074         static const std::string paramPoseEstimatorModel;
00075
00079         Ort::Env m_ortenv;
00080
00084         std::unique_ptr<Ort::Session> m_ort_session;
00085
00089         int64_t m_expected_image_width = 0;
00090
00094         int64_t m_expected_image_height = 0;
00095
00099         int64_t m_expected_image_number_of_channels = 0;
00100
00104         int64_t m_number_of_input_elements = 0;
00105
00109         std::array<int64_t, 4> inputShape;
00110
00118         cv::Mat CropImage(const cv::Mat& image, const OFIQ::BoundingBox& biggestFace);
00119     };
00120 }

```

8.85 poseEstimators.h File Reference

Base class for the different implementation of pose estimation algorithms.

```

#include "ofiq_lib.h"
#include "Session.h"
#include <array>

```

Classes

- class [OFIQ_LIB::PoseEstimatorInterface](#)

Implementation of the base class for integrating pose estimation algorithms capable of estimating three head orientation angles (yaw, pitch and roll) from a face image.

Namespaces

- namespace [OFIQ_LIB](#)

Namespace for OFIQ implementations.

8.85.1 Detailed Description

Base class for the different implementation of pose estimation algorithms.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.86 poseEstimators.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "Session.h"
00031 #include <array>
00032
00036 namespace OFIQ_LIB
00037 {
00038
00043     class PoseEstimatorInterface
00044     {
00045     public:
00046         using EulerAngle = std::array<double, 3>;
00047
00052         virtual ~PoseEstimatorInterface() = default;
00053
00061         EulerAngle& estimatePose(OFIQ_LIB::Session& session);
00062
00063     protected:
00070         virtual void updatePose(OFIQ_LIB::Session& session, EulerAngle& pose) = 0;
00071
00072     private:
00077         std::string lastSessionId;
00078
00083         EulerAngle pose;
00084     };
00085 }
```

8.87 FaceOcclusionSegmentation.h File Reference

Provides a class for segmenting the facial part not occluded by any non-facial parts from an image.

```
#include "Configuration.h"
#include "segmentations.h"
#include <ONNXRTSegmentation.h>
```

Classes

- class [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation](#)
Class managing the separation of facial parts not occluded by non-facial parts from other parts.

Namespaces

- namespace [cv](#)
OpenCV's namespace.
- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::segmentations](#)
Provides segmentation-related implementations.

8.87.1 Detailed Description

Provides a class for segmenting the facial part not occluded by any non-facial parts from an image.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.88 FaceOcclusionSegmentation.h

[Go to the documentation of this file.](#)

```

00001
00028 #pragma once
00029
00030 #include "Configuration.h"
00031 #include "segmentations.h"
00032 #include <ONNXRTSegmentation.h>
00033
00037 namespace cv
00038 {
00042     class Mat;
00043 }
00044
00048 namespace OFIQ_LIB::modules::segmentations
00049 {
00056     class FaceOcclusionSegmentation : public SegmentationExtractorInterface
00057     {
00058     public:
00065         explicit FaceOcclusionSegmentation(const Configuration& config);
00066
00070         ~FaceOcclusionSegmentation() override = default;
00071
00072     protected:
00073         OFIQ::Image UpdateMask(
00093             OFIQ_LIB::Session& session, modules::segmentations::SegmentClassLabels faceSegment)
00094     override;
00095
00096     private:
00097
00105         cv::Mat GetFaceOcclusionSegmentation(const cv::Mat& alignedImage);
00106
00110         ONNXRuntimeSegmentation m_onnxRuntimeEnv;
00111
00117         std::shared_ptr<cv::Mat> segmentationImage;
00118
00123         const std::string modelConfigItem = "params.measures.FaceOcclusionSegmentation.model_path";
00124
00128         const int cropLeft = 96;
00129
00133         const int cropRight = 96;
00134
00138         const int cropTop = 96;
00139
00143         const int cropBottom = 96;
00144
00150         const int scaledWidth = 224;
00151
00157         const int scaledHeight = 224;
00158
00159     };
00160 }

```

8.89 FaceParsing.h File Reference

Provides a class implementing the face parsing pre-processing.

```

#include "Configuration.h"
#include "segmentations.h"
#include <ONNXRTSegmentation.h>

```

Classes

- class [OFIQ_LIB::modules::segmentations::FaceParsing](#)
Class managing the separation of facial parts not occluded by non-facial parts from other parts.

Namespaces

- namespace `cv`
OpenCV's namespace.
- namespace `OFIQ_LIB`
Namespace for OFIQ implementations.
- namespace `OFIQ_LIB::modules`
- namespace `OFIQ_LIB::modules::segmentations`
Provides segmentation-related implementations.

8.89.1 Detailed Description

Provides a class implementing the face parsing pre-processing.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.90 FaceParsing.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "Configuration.h"
00031 #include "segmentations.h"
00032
00033 #include <ONNXRTSegmentation.h>
00034
00038 namespace cv
00039 {
00043     class Mat;
00044 }
00045
00049 namespace OFIQ_LIB::modules::segmentations
00050 {
00083     class FaceParsing : public SegmentationExtractorInterface
00084     {
00085     public:
```

```

00092     explicit FaceParsing(const Configuration& config);
00093
00097     ~FaceParsing() override = default;
00098
00099
00100     protected:
00126         OFIQ::Image UpdateMask(
00127             OFIQ_LIB::Session& session, modules::segmentations::SegmentClassLabels faceSegment)
00128     override;
00129
00129     private:
00130
00134         ONNXRuntimeSegmentation m_onnxRuntimeEnv;
00135
00141         std::shared_ptr<cv::Mat> segmentationImage;
00142
00148         const std::string modelConfigItem = "params.measures.FaceParsing.model_path";
00149
00153         const int imageSize = 400;
00154
00158         const int cropLeft = 30;
00159
00163         const int cropRight = 30;
00164
00168         const int cropTop = 0;
00169
00173         const int cropBottom = 60;
00174
00183         static cv::Mat CreateBlob(const cv::Mat& image, int i_imageSize_one_dim);
00184
00196         static std::shared_ptr<cv::Mat> CalculateClassIds(
00197             const cv::Mat& resultImage,
00198             int i_imageSize_one_dim);
00199
00200         /**
00201          * @brief Derives the private member \link segmentationImage\endlink
00202          * from the facial image data provided by the session object.
00203          * @details Implements CNN processing step of \link
00204 OFIQ_LIB::modules::segmentations::FaceParsing::UpdateMask()
00205          * UpdateMask()\endlink.
00206          * @param session Session object containing the original facial image and pre-processing
00207          results
00208          * computed by the \link OFIQ_LIB::OFIQImpl::performPreprocessing()
00209          * OFIQImpl::performPreprocessing()\endlink method.
00210          */
00209         void SetImage(OFIQ_LIB::Session& session);
00210     };
00211 }

```

8.91 ONNXRTSegmentation.h File Reference

Helper class to manage the ONNXRuntime session object.

```

#include <vector>
#include <opencv2/opencv.hpp>
#include <onnxruntime_cxx_api.h>

```

Classes

- class [ONNXRuntimeSegmentation](#)
Helper class to manage the ONNXRuntime session object.

8.91.1 Detailed Description

Helper class to manage the ONNXRuntime session object.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.92 ONNXRTSegmentation.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include <vector>
00030
00031 #include <opencv2/opencv.hpp>
00032 #include <onnxruntime_cxx_api.h>
00033
00039 class ONNXRuntimeSegmentation
00040 {
00041 private:
00042
00047     Ort::Env m_ortenv;
00048
00053     Ort::MemoryInfo m_memory_info = Ort::MemoryInfo::CreateCpu(OrtDeviceAllocator, OrtMemTypeCPU);
00054
00059     std::array<int64_t, 4> m_inputShape;
00060
00065     std::unique_ptr<Ort::Session> m_ort_session;
00066
00074     void init_session(const std::vector<uint8_t>& i_model_data, int64_t i_imageWidth, int64_t
00075 i_imageHeight);
00076
00077 public:
00082     ONNXRuntimeSegmentation() = default;
00083
00088     ~ONNXRuntimeSegmentation() = default;
00089
00097     void initialize(
00098         const std::vector<uint8_t>& i_modelData, int64_t i_imageWidth, int64_t i_imageHeight);
00099
00105     size_t getNumberOfOutputNodes();
00106
00113     std::vector<Ort::Value> run( std::vector<float>& i_netInput);
00114
00115 };
```

8.93 segmentations.h File Reference

Base class for the different implementation of segmentation algorithms.

```
#include "ofiq_lib.h"
#include "Session.h"
```

Classes

- class [OFIQ_LIB::SegmentationExtractorInterface](#)
Base class for the different implementation of segmentation algorithms.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.
- namespace [OFIQ_LIB::modules](#)
- namespace [OFIQ_LIB::modules::segmentations](#)
Provides segmentation-related implementations.

Enumerations

- enum class [OFIQ_LIB::modules::segmentations::SegmentClassLabels](#) {
[OFIQ_LIB::modules::segmentations::background](#) , [OFIQ_LIB::modules::segmentations::skin](#) , [OFIQ_LIB::modules::segmentations::r_brow](#) ,
[OFIQ_LIB::modules::segmentations::l_eye](#) , [OFIQ_LIB::modules::segmentations::r_eye](#) , [OFIQ_LIB::modules::segmentations::l_ear](#) ,
[OFIQ_LIB::modules::segmentations::r_ear](#) , [OFIQ_LIB::modules::segmentations::ear_r](#) , [OFIQ_LIB::modules::segmentations::mouth](#) ,
[OFIQ_LIB::modules::segmentations::u_lip](#) , [OFIQ_LIB::modules::segmentations::l_lip](#) , [OFIQ_LIB::modules::segmentations::neck_l](#) ,
[OFIQ_LIB::modules::segmentations::neck_r](#) , [OFIQ_LIB::modules::segmentations::cloth](#) , [OFIQ_LIB::modules::segmentations::hair](#) , [OFIQ_LIB::modules::segmentations::face](#) }
Enum class of the different face regions that can be segmented.

8.93.1 Detailed Description

Base class for the different implementation of segmentation algorithms.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.94 segmentations.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "Session.h"
00031
00035 namespace OFIQ_LIB
00036 {
00040     namespace modules::segmentations
00041     {
00045         enum class SegmentClassLabels
00046         {
00050             background,
00054             skin,
00058             l_brow,
00062             r_brow,
00066             l_eye,
00070             r_eye,
00074             eye_g,
00078             l_ear,
00082             r_ear,
00086             ear_r,
00090             nose,
00094             mouth,
00098             u_lip,
00102             l_lip,
00106             neck,
00110             neck_l,
00114             cloth,
00118             hair,
00122             hat,
00126             face
00127         };
00128     }
00129
00137 class SegmentationExtractorInterface
00138 {
00139 public:
00144     virtual ~SegmentationExtractorInterface() = default;
00145
00153     OFIQ::Image& GetMask(
00154         OFIQ_LIB::Session& session, modules::segmentations::SegmentClassLabels faceSegment);
00155
00156 protected:
00157
00165     virtual OFIQ::Image UpdateMask(
00166         OFIQ_LIB::Session& session,
00167         modules::segmentations::SegmentClassLabels faceSegment) = 0;
00168
00173     std::string GetLastSessionId() const { return lastSessionId; };
00174
00175 private:
00180     std::string lastSessionId;
00185     std::map<modules::segmentations::SegmentClassLabels, OFIQ::Image> masks;
00186 };
00187 }

```

8.95 Configuration.h File Reference

Provides a configuration class for handling configurations.

```

#include <map>
#include <string>
#include <filesystem>
#include <tao/json/forward.hpp>
#include <tao/json/value.hpp>

```

Classes

- class `OFIQ_LIB::Configuration`
Configuration class.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

8.95.1 Detailed Description

Provides a configuration class for handling configurations.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.96 Configuration.h

[Go to the documentation of this file.](#)

```
00001
00029 #pragma once
00030
00031 #include <map>
00032 #include <string>
00033 #include <filesystem>
00034
00035 #include <tao/json/forward.hpp>
00036 #include <tao/json/value.hpp>
00037
00041 namespace OFIQ_LIB
00042 {
00049     class Configuration
00050     {
00051     public:
00058         Configuration(const std::string& configDir, const std::string& configFilename);
00059
00068         bool GetBool(const std::string& key, bool& value) const;
00069
00078         bool GetString(const std::string& key, std::string& value) const;
00079
00089         bool GetNumber(const std::string& key, double& value) const;
00090
00102         bool GetStringList(const std::string& key, std::vector<std::string>& value) const;
00103
00110         bool GetBool(const std::string& key) const;
00111
```

```
00118     std::string GetString(const std::string& key) const;
00119
00126     double GetNumber(const std::string& key) const;
00127
00135     std::string getDataDir() const;
00136
00143     void setDataDir(std::string dataDir);
00144
00145     private:
00149     std::map<std::string, tao::json::value, std::less<> > parameters;
00150
00156     std::filesystem::path m_dataDir;
00157 };
00158 }
```

8.97 image_io.h File Reference

Provides helper functions for reading/writing images from/to disk.

```
#include "ofiq_lib.h"
```

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

Functions

- [OFIQ_EXPORT OFIQ::ReturnStatus OFIQ_LIB::readImage](#) (const std::string &filename, [OFIQ::Image](#) &image)
Read image from disk.

8.97.1 Detailed Description

Provides helper functions for reading/writing images from/to disk.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.98 image_io.h

[Go to the documentation of this file.](#)

```
00001
00027 #ifndef OFIQ_LIB_IMAGE_IO_H
00028 #define OFIQ_LIB_IMAGE_IO_H
00029
00030 #include "ofiq_lib.h"
00031
00035 namespace OFIQ_LIB {
00036
00044     OFIQ_EXPORT OFIQ::ReturnStatus
00045         readImage(const std::string& filename, OFIQ::Image& image);
00046 }
00047
00048 #endif
```

8.99 image_utils.h File Reference

Provides image utility functions such as color conversion, luminance computation etc.

```
#include "ofiq_lib.h"
#include "Session.h"
#include <opencv2/imgcodecs.hpp>
#include <opencv2/imgproc.hpp>
```

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

Typedefs

- using [OFIQ_LIB::ExposureRange](#) = `std::array<int, 2>`

Functions

- [OFIQ_EXPORT](#) double [OFIQ_LIB::ColorConvert](#) (double v)
Converts a color as specified in ISO/IEC 29794-5.
- [OFIQ_EXPORT](#) double [OFIQ_LIB::Cubic](#) (double x, double k, double eps)
Cubic flattening function.
- [OFIQ_EXPORT](#) void [OFIQ_LIB::ConvertBGRToCIELAB](#) (const cv::Mat &bgrImage, double &a, double &b)
Computes CIELAB values a^ and b^* from a BGR image.*
- [OFIQ_EXPORT](#) cv::Mat [OFIQ_LIB::GetLuminanceImageFromBGR](#) (const cv::Mat &bgrImage)
Converts a BGR image to the luminance image.
- [OFIQ_EXPORT](#) void [OFIQ_LIB::CalculateReferencePoints](#) (const [OFIQ::FaceLandmarks](#) &landmarks, [OFIQ::LandmarkPoint](#) &leftEyeCenter, [OFIQ::LandmarkPoint](#) &rightEyeCenter, double &interEyeDistance, double &eyeMouthDistance)
Computes the left eye center, the right eye center, the (planar) inter-eye-distance and the eye to mouth distance from facial landmarks.
- [OFIQ_EXPORT](#) void [OFIQ_LIB::CalculateRegionOfInterest](#) (cv::Rect &leftRegionOfInterest, cv::Rect &rightRegionOfInterest, const [OFIQ::LandmarkPoint](#) &leftEyeCenter, const [OFIQ::LandmarkPoint](#) &rightEyeCenter, const double interEyeDistance, const double eyeMouthDistance)

Extracts regions being of interest for some measures (e.g. NaturalColour).

- **OFIQ_EXPORT** void **OFIQ_LIB::GetNormalizedHistogram** (const cv::Mat &luminanceImage, const cv::Mat &maskImage, cv::Mat1f &histogram)

Computes the normalized histogram from a luminance image in 256 chunks.

- **OFIQ_EXPORT** double **OFIQ_LIB::CalculateExposure** (const **Session** &session, const **ExposureRange** &exposureRange)

Helper function for some measures.

- **OFIQ_EXPORT** double **OFIQ_LIB::ComputeBrightnessAspect** (const cv::Mat &luminanceImage, const cv::Mat &maskImage, const **ExposureRange** &exposureRange)

Helper function for some measures.

8.99.1 Detailed Description

Provides image utility functions such as color conversion, luminance computation etc.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.100 image_utils.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028
00029 #include "ofiq_lib.h"
00030 #include "Session.h"
00031 #include <opencv2/imgcodecs.hpp>
00032 #include <opencv2/imgproc.hpp>
00033
00037 namespace OFIQ_LIB {
00038
00039     using ExposureRange = std::array<int, 2>;
00040
00047     OFIQ_EXPORT double ColorConvert(double v);
00048
00057     OFIQ_EXPORT double Cubic(double x, double k, double eps);
00058
00065     OFIQ_EXPORT void ConvertBGRToCIELAB(const cv::Mat& bgrImage, double& a, double& b);
```

```

00066
00074     OFIQ_EXPORT cv::Mat GetLuminanceImageFromBGR(const cv::Mat& bgrImage );
00075
00085     OFIQ_EXPORT void CalculateReferencePoints(const OFIQ::FaceLandmarks& landmarks,
00086         OFIQ::LandmarkPoint& leftEyeCenter,
00087         OFIQ::LandmarkPoint& rightEyeCenter,
00088         double& interEyeDistance,
00089         double& eyeMouthDistance);
00090
00104     OFIQ_EXPORT void CalculateRegionOfInterest(cv::Rect& leftRegionOfInterest,
00105         cv::Rect& rightRegionOfInterest,
00106         const OFIQ::LandmarkPoint& leftEyeCenter,
00107         const OFIQ::LandmarkPoint& rightEyeCenter,
00108         const double interEyeDistance, const double eyeMouthDistance);
00109
00117     OFIQ_EXPORT void GetNormalizedHistogram(const cv::Mat& luminanceImage, const cv::Mat& maskImage,
cv::Mat1f& histogram);
00118
00132     OFIQ_EXPORT double CalculateExposure(const Session& session, const ExposureRange& exposureRange);
00133
00145     OFIQ_EXPORT double ComputeBrightnessAspect(
00146         const cv::Mat& luminanceImage, const cv::Mat& maskImage, const ExposureRange& exposureRange);
00147 }

```

8.101 NeuronalNetworkContainer.h File Reference

```

#include "detectors.h"
#include "landmarks.h"
#include "segmentations.h"
#include "poseEstimators.h"

```

Classes

- struct [OFIQ_LIB::NeuronalNetworkContainer](#)
Neural network container for OFIQ's preprocessing steps.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

8.102 NeuronalNetworkContainer.h

[Go to the documentation of this file.](#)

```

00001
00027 #pragma once
00028 #include "detectors.h"
00029 #include "landmarks.h"
00030 #include "segmentations.h"
00031 #include "poseEstimators.h"
00032
00036 namespace OFIQ_LIB
00037 {
00041     struct NeuronalNetworkContainer
00042     {
00055         NeuronalNetworkContainer(
00056             std::shared_ptr<FaceDetectorInterface> faceDetector,
00057             std::shared_ptr<FaceLandmarkExtractorInterface> landmarkExtractor,
00058             std::shared_ptr<SegmentationExtractorInterface> segmentationExtractor,
00059             std::shared_ptr<PoseEstimatorInterface> poseEstimator,
00060             std::shared_ptr<SegmentationExtractorInterface> faceOcclusionExtractor
00061         )
00062         : faceDetector{faceDetector},

```



```
00063         landmarkExtractor{landmarkExtractor},
00064         segmentationExtractor{segmentationExtractor},
00065         poseEstimator{poseEstimator},
00066         faceOcclusionExtractor{faceOcclusionExtractor}
00067     {
00068     }
00069
00073     std::shared_ptr<FaceDetectorInterface> faceDetector;
00074
00078     std::shared_ptr<FaceLandmarkExtractorInterface> landmarkExtractor;
00079
00085     std::shared_ptr<SegmentationExtractorInterface> segmentationExtractor;
00086
00092     std::shared_ptr<SegmentationExtractorInterface> faceOcclusionExtractor;
00093
00097     std::shared_ptr<PoseEstimatorInterface> poseEstimator;
00098 };
00099 }
```

8.103 OFIQError.h File Reference

Provides a class for the error handling within the QFIQ.

```
#include "ofiq_lib.h"
#include <string_view>
```

Classes

- class [OFIQ_LIB::OFIQError](#)
Implementation of a custom exception.

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

8.103.1 Detailed Description

Provides a class for the error handling within the QFIQ.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.104 OFIQError.h

[Go to the documentation of this file.](#)

```
00001
00027 #pragma once
00028 #include "ofiq_lib.h"
00029 #include <string_view>
00030
00034 namespace OFIQ_LIB
00035 {
00040     class OFIQError : public std::exception
00041     {
00042     public:
00049         OFIQError(OFIQ::ReturnCode returnCode, std::string_view message);
00050
00056         const char* what() const noexcept override { return extendedMessage.c_str(); }
00057
00063         OFIQ::ReturnCode whatCode() const noexcept { return returnCode; }
00064
00065     private:
00070         OFIQ::ReturnCode returnCode;
00071
00076         std::string message;
00077
00082         std::string extendedMessage;
00083     };
00084 }
```

8.105 Session.h File Reference

The session class is the data container used to distribute the image and additional data, including the data computed during the pre-processing.

```
#include "ofiq_lib.h"
#include <opencv2/opencv.hpp>
```

Classes

- class [OFIQ_LIB::Session](#)

Namespaces

- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

Typedefs

- using [OFIQ_LIB::EulerAngle](#) = std::array<double, 3>

8.105.1 Detailed Description

The session class is the data container used to distribute the image and additional data, including the data computed during the pre-processing.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.106 Session.h

[Go to the documentation of this file.](#)

```
00001
00028 #pragma once
00029
00030 #include "ofiq_lib.h"
00031 #include <opencv2/opencv.hpp>
00032
00036 namespace OFIQ_LIB
00037 {
00041     struct NeuronalNetworkContainer;
00042
00043     using EulerAngle = std::array<double, 3>;
00044
00051     class Session
00052     {
00053     public:
00054
00061         Session(const OFIQ::Image& image, OFIQ::FaceImageQualityAssessment& assessment)
00062             : _image{image},
00063               _assessment{assessment},
00064               id{GenerateId()}
00065         {
00066         }
00067
00072         const OFIQ::Image& image() const { return _image; }
00073
00078         OFIQ::FaceImageQualityAssessment& assessment() { return _assessment; }
00079
00085         const std::string& Id() const { return id; }
00086
00087         // use the session object as data container
00088
00094         void setDetectedFaces(const std::vector<OFIQ::BoundingBox>& i_boundingBoxes);
00095
00101         std::vector<OFIQ::BoundingBox> getDetectedFaces() const;
00102
```

```

00103 #ifdef OFIQ_SINGLE_FACE_PRESENT_WITH_TMETRIC
00104     void setLandmarksAllFaces(const std::vector<OFIQ::FaceLandmarks>& i_detectedLandmarks);
00105     std::vector<OFIQ::FaceLandmarks> getLandmarksAllFaces() const;
00106 #endif
00107
00113     void setPose(const EulerAngle& i_pose);
00114
00120     EulerAngle getPose() const;
00121
00127     void setLandmarks(const OFIQ::FaceLandmarks& i_landmarks);
00128
00134     OFIQ::FaceLandmarks getLandmarks() const;
00135
00136
00142     void setAlignedFaceLandmarks(const OFIQ::FaceLandmarks& i_landmarks);
00143
00149     OFIQ::FaceLandmarks getAlignedFaceLandmarks() const;
00150
00156     void setAlignedFaceTransformationMatrix(const cv::Mat & i_transformationMatrix);
00157
00158
00164     cv::Mat getAlignedFaceTransformationMatrix() const;
00165
00166
00172     void setAlignedFace(const cv::Mat & i_alignedFace);
00173
00179     cv::Mat getAlignedFace() const;
00180
00186     void setAlignedFaceLandmarkedRegion(const cv::Mat & i_alignedFaceRegion);
00187
00193     cv::Mat getAlignedFaceLandmarkedRegion() const;
00194
00200     void setFaceParsingImage(const cv::Mat& i_parsingImage);
00201
00207     cv::Mat getFaceParsingImage() const;
00208
00214     void setFaceOcclusionSegmentationImage(const cv::Mat & i_segmentationImage);
00215
00221     cv::Mat getFaceOcclusionSegmentationImage() const;
00222
00223     private:
00228         const OFIQ::Image& _image;
00229
00234         OFIQ::FaceImageQualityAssessment& _assessment;
00239         std::vector<OFIQ::BoundingBox> detectedFaces;
00240
00241 #ifdef OFIQ_SINGLE_FACE_PRESENT_WITH_TMETRIC
00242     std::vector<OFIQ::FaceLandmarks> landmarksAllFaces;
00243 #endif
00244
00249     EulerAngle pose;
00250
00255     OFIQ::FaceLandmarks landmarks;
00256
00261     OFIQ::FaceLandmarks alignedFaceLandmarks;
00262
00267     cv::Mat alignedFaceTransformationMatrix;
00268
00273     cv::Mat alignedFace;
00274
00279     cv::Mat alignedFacelandmarkedRegion;
00280
00285     cv::Mat faceParsingImage;
00286
00291     cv::Mat faceOcclusionSegmentationImage;
00292
00298     std::string GenerateId() const;
00299
00304     std::string id;
00305 };
00306 }

```

8.107 utils.h File Reference

Helper functions used by several classes.

```
#include "ofiq_lib.h"
```

Classes

- struct [Point2f](#)
Representation of a point with floating point arithmetics.
- struct [OFIQ_LIB::Point2i](#)
Representation of a point with integer arithmetics.

Namespaces

- namespace [cv](#)
OpenCV's namespace.
- namespace [OFIQ_LIB](#)
Namespace for OFIQ implementations.

Functions

- [OFIQ_EXPORT](#) void [OFIQ_LIB::makeSquareBoundingBoxWithPadding](#) (const [OFIQ::BoundingBox](#) &i↔_bb, const cv::Mat &i_input_image, cv::Mat &o_output_image, [OFIQ::BoundingBox](#) &o_bb, [Point2i](#) &o↔_translation_vector)
Some computations, especially neural networks, need a squarred image as input. This funtion consumes a boundig box and an input image. The greater parameter of width or height is used to define the side length of the new squarred bounding box. The face will be centered in the bounding box. Padding is added if needed. The squarred bounding box is used generate a new cropped image, the o_output_image. Required translations are described by the translation vector o_translation_vector.
- [OFIQ_EXPORT](#) [OFIQ::BoundingBox](#) [OFIQ_LIB::makeSquareBoundingBox](#) (const [OFIQ::BoundingBox](#) &i↔_bb)
This function converts a non-squarred bounding box into an squarred one. The side length is defined by the greater one of height or width.
- [OFIQ_EXPORT](#) size_t [OFIQ_LIB::findLargestBoundingBox](#) (const std::vector< [OFIQ::BoundingBox](#) > &faceRects)
This function returns the position of the largest bounding box (largest in terms of area) from a vector of bounding boxes.
- [OFIQ_EXPORT](#) cv::Mat [OFIQ_LIB::copyToCvImage](#) (const [OFIQ::Image](#) &sourceImage, bool asGray↔_Image=false)
Convert images in OFIQ::Image format into the OpenCV cv::Mat format. The image can be converted from color to gray scale by setting the parameter asGrayImage to true.
- [OFIQ_EXPORT](#) cv::Mat [OFIQ_LIB::alignImage](#) (const [OFIQ::Image](#) &faceImage, const [OFIQ::FaceLandmarks](#) &faceLandmarks, [OFIQ::FaceLandmarks](#) &alignedFaceLandmarks, cv::Mat &transformationMatrix)
This function transforms a face image so that the position of the eyes, nose and mouth are roughly at a pre-defined position. Face alignment is the translation, rotation and scaling of the image to do this.
- [OFIQ_EXPORT](#) void [OFIQ_LIB::calculateEyeCenter](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks, [Point2f](#) &leftEyeCenter, [Point2f](#) &rightEyeCenter)
Based on face landmarks the center of the left and right eye are computed.
- [OFIQ_EXPORT](#) [OFIQ::Image](#) [OFIQ_LIB::MakeGreyImage](#) (uint16_t width, uint16_t height)
This function generates a gray scaled image with the resolution passed by the call.
- [OFIQ_EXPORT](#) float [OFIQ_LIB::tmetric](#) (const [OFIQ::FaceLandmarks](#) &faceLandmarks)
Based on the provided landmarks this function computes the distance between the point between the eyes and the chin.
- [OFIQ_EXPORT](#) void [OFIQ_LIB::rotationMatrixToEulerAngles](#) (const cv::Mat &R, std::vector< double > &angles)
Based on a given rotation matrix this functions computes and returns the corresponding Euler angles.

8.107.1 Detailed Description

Helper functions used by several classes.

Copyright

Copyright (c) 2024 Federal Office for Information Security, Germany

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Author

OFIQ development team

8.108 utils.h

[Go to the documentation of this file.](#)

```
00001
00027 #ifndef OFIQ_LIB_UTILS_H
00028 #define OFIQ_LIB_UTILS_H
00029
00030 #include "ofiq_lib.h"
00031
00035 namespace cv
00036 {
00040     class Mat;
00041 }
00042
00047 struct Point2f
00048 {
00049     float x;
00050     float y;
00051 };
00052
00053
00054
00055 namespace OFIQ_LIB
00056 {
00061     struct Point2i
00062     {
00063         int x;
00064         int y;
00065     };
00066
00081     OFIQ_EXPORT void makeSquareBoundingBoxWithPadding(
00082         const OFIQ::BoundingBox& i_bb,
00083         const cv::Mat& i_input_image,
00084         cv::Mat& o_output_image,
00085         OFIQ::BoundingBox& o_bb,
00086         Point2i & o_translation_vector
00087     );
00088
00095     OFIQ_EXPORT OFIQ::BoundingBox makeSquareBoundingBox(
00096         const OFIQ::BoundingBox& i_bb);
```

```
00097
00104     OFIQ_EXPORT size_t findLargestBoundingBox(
00105         const std::vector<OFIQ::BoundingBox>& faceRects);
00106
00114     OFIQ_EXPORT cv::Mat copyToCvImage(const OFIQ::Image& sourceImage, bool asGrayImage = false);
00115
00125     OFIQ_EXPORT cv::Mat alignImage(
00126         const OFIQ::Image& faceImage,
00127         const OFIQ::FaceLandmarks& faceLandmarks,
00128         OFIQ::FaceLandmarks& alignedFaceLandmarks,
00129         cv::Mat& transformationMatrix);
00130
00138     OFIQ_EXPORT void calculateEyeCenter(
00139         const OFIQ::FaceLandmarks& faceLandmarks,
00140         Point2f& leftEyeCenter,
00141         Point2f& rightEyeCenter);
00142
00150     OFIQ_EXPORT OFIQ::Image MakeGreyImage(uint16_t width, uint16_t height);
00151
00158     OFIQ_EXPORT float tmetric(const OFIQ::FaceLandmarks& faceLandmarks);
00159
00166     OFIQ_EXPORT void rotationMatrixToEulerAngles(const cv::Mat& R, std::vector<double>& angles);
00167 }
00168
00169 #endif
```


Index

- [_assessment](#)
 - [OFIQ_LIB::Session, 180](#)
 - [_image](#)
 - [OFIQ_LIB::Session, 180](#)
 - [~ADNetFaceLandmarkExtractor](#)
 - [OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor, 58](#)
 - [~FaceDetectorInterface](#)
 - [OFIQ_LIB::FaceDetectorInterface, 87](#)
 - [~FaceLandmarkExtractorInterface](#)
 - [OFIQ_LIB::FaceLandmarkExtractorInterface, 90](#)
 - [~FaceOcclusionSegmentation](#)
 - [OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 100](#)
 - [~FaceParsing](#)
 - [OFIQ_LIB::modules::segmentations::FaceParsing, 104](#)
 - [~HeadPose3DDFAV2](#)
 - [OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 111](#)
 - [~Interface](#)
 - [OFIQ::Interface, 123](#)
 - [~Measure](#)
 - [OFIQ_LIB::modules::measures::Measure, 132](#)
 - [~OFIQImpl](#)
 - [OFIQ_LIB::OFIQImpl, 154](#)
 - [~ONNXRuntimeSegmentation](#)
 - [ONNXRuntimeSegmentation, 158](#)
 - [~PoseEstimatorInterface](#)
 - [OFIQ_LIB::PoseEstimatorInterface, 166](#)
 - [~SSDFaceDetector](#)
 - [OFIQ_LIB::modules::detectors::SSDFaceDetector, 192](#)
 - [~SegmentationExtractorInterface](#)
 - [OFIQ_LIB::SegmentationExtractorInterface, 171](#)
- [a](#)
 - [OFIQ_LIB::modules::measures::SigmoidParameters, 187](#)
- [AddSigmoid](#)
 - [OFIQ_LIB::modules::measures::Measure, 132](#)
- [adnet_FaceMap.h, 211, 213](#)
- [adnet_landmarks.h, 214, 215](#)
- [ADNetFaceLandmarkExtractor](#)
 - [OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor, 58](#)
- [alignedFace](#)
 - [OFIQ_LIB::Session, 180](#)
- [alignedFacelandmarkedRegion](#)
 - [OFIQ_LIB::Session, 180](#)
- [alignedFaceLandmarks](#)
 - [OFIQ_LIB::Session, 180](#)
- [alignedFaceTransformationMatrix](#)
 - [OFIQ_LIB::Session, 180](#)
- [alignFaceImage](#)
 - [OFIQ_LIB::OFIQImpl, 154](#)
- [alignImage](#)
 - [OFIQ_LIB, 37](#)
- [AllDetectors.h, 208](#)
- [AllLandmarks.h, 216](#)
- [AllMeasures.h, 223, 224](#)
- [AllPoseEstimators.h, 259, 260](#)
- [Assessment](#)
 - [OFIQ_LIB::Session, 175](#)
- [background](#)
 - [OFIQ_LIB::modules::segmentations, 55](#)
- [BackgroundUniformity](#)
 - [OFIQ, 33](#)
 - [OFIQ_LIB::modules::measures::BackgroundUniformity, 61](#)
- [BackgroundUniformity.h, 224, 226](#)
- [BoundingBox](#)
 - [OFIQ::BoundingBox, 63](#)
- [boundingBox](#)
 - [OFIQ::FaceImageQualityAssessment, 89](#)
- [CalculateClassIds](#)
 - [OFIQ_LIB::modules::segmentations::FaceParsing, 105](#)
- [CalculateExposure](#)
 - [OFIQ_LIB, 38](#)
- [calculateEyeCenter](#)
 - [OFIQ_LIB, 38](#)
- [CalculateReferencePoints](#)
 - [OFIQ_LIB, 38](#)
- [CalculateRegionOfInterest](#)
 - [OFIQ_LIB, 39](#)
- [CalculateScore](#)
 - [OFIQ_LIB::modules::measures::NaturalColour, 144](#)
- [CHIN](#)
 - [OFIQ_LIB::modules::landmarks, 48](#)
- [chin](#)
 - [OFIQ_LIB::modules::landmarks::adnet, 49](#)
- [classifier](#)
 - [OFIQ_LIB::modules::measures::ExpressionNeutrality, 81](#)
- [cloth](#)
 - [OFIQ_LIB::modules::segmentations, 56](#)

- code
 - OFIQ::QualityMeasureResult, 168
 - OFIQ::ReturnStatus, 169
- ColorConvert
 - OFIQ_LIB, 39
- CompressionArtifacts
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::CompressionArtifacts, 66
- CompressionArtifacts.h, 226, 227
- ComputeBrightnessAspect
 - OFIQ_LIB, 40
- confidenceThreshold
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 192
- config
 - OFIQ_LIB::OFIQImpl, 156
- Configuration
 - OFIQ_LIB::Configuration, 69
- configuration
 - OFIQ_LIB::modules::measures::Measure, 136
- Configuration.h, 269, 270
- contour
 - OFIQ_LIB::modules::landmarks::adnet, 49
- ConvertBGRToCIELAB
 - OFIQ_LIB, 40
- copyToCvImage
 - OFIQ_LIB, 40
- CreateBlob
 - OFIQ_LIB::modules::segmentations::FaceParsing, 105
- CreateExecutor
 - OFIQ_LIB::OFIQImpl, 154
- CreateMaskedImage
 - OFIQ_LIB::modules::measures::NaturalColour, 145
- CreateMeasure
 - OFIQ_LIB::modules::measures::MeasureFactory, 137
- CreateNetworks
 - OFIQ_LIB::OFIQImpl, 155
- cropBottom
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 106
- CropImage
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 112
- cropLeft
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 106
- CropOfTheFacelImage
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::CropOfTheFacelImage, 74
- CropOfTheFacelImage.h, 227, 228
- cropRight
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 106
- cropTop
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 107
- Cubic
 - OFIQ_LIB, 41
- cv, 31
- data
 - OFIQ::Image, 119
- depth
 - OFIQ::Image, 119
- detectedFaces
 - OFIQ_LIB::Session, 180
- detectFaces
 - OFIQ_LIB::FaceDetectorInterface, 87
- detectors.h, 209, 210
- dnnNet
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 192
- DownwardCropOfTheFacelImage
 - OFIQ, 34
- dummyAssesment
 - OFIQ_LIB::OFIQImpl, 156
- dummyImage
 - OFIQ_LIB::OFIQImpl, 156
- DynamicRange
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::DynamicRange, 76
- DynamicRange.h, 229, 230
- ear_r
 - OFIQ_LIB::modules::segmentations, 56
- estimatePose
 - OFIQ_LIB::PoseEstimatorInterface, 166
- EulerAngle
 - OFIQ_LIB, 37
 - OFIQ_LIB::PoseEstimatorInterface, 165
- execLogActive
 - OFIQ_LIB::modules::measures, 54
- Execute
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 61
 - OFIQ_LIB::modules::measures::CompressionArtifacts, 67
 - OFIQ_LIB::modules::measures::CropOfTheFacelImage, 75
 - OFIQ_LIB::modules::measures::DynamicRange, 77
 - OFIQ_LIB::modules::measures::ExpressionNeutrality, 81

- OFIQ_LIB::modules::measures::EyesOpen, [83](#)
- OFIQ_LIB::modules::measures::EyesVisible, [86](#)
- OFIQ_LIB::modules::measures::FaceOcclusionPrevention, [97](#)
- OFIQ_LIB::modules::measures::HeadPose, [109](#)
- OFIQ_LIB::modules::measures::HeadSize, [115](#)
- OFIQ_LIB::modules::measures::IlluminationUniformity, [118](#)
- OFIQ_LIB::modules::measures::InterEyeDistance, [122](#)
- OFIQ_LIB::modules::measures::Luminance, [129](#)
- OFIQ_LIB::modules::measures::Measure, [133](#)
- OFIQ_LIB::modules::measures::MouthClosed, [140](#)
- OFIQ_LIB::modules::measures::MouthOcclusionPrevention, [142](#)
- OFIQ_LIB::modules::measures::NaturalColour, [145](#)
- OFIQ_LIB::modules::measures::NoHeadCoverings, [150](#)
- OFIQ_LIB::modules::measures::OverExposurePrevention, [162](#)
- OFIQ_LIB::modules::measures::Sharpness, [184](#)
- OFIQ_LIB::modules::measures::SingleFacePresent, [190](#)
- OFIQ_LIB::modules::measures::UnderExposurePrevention, [195](#)
- OFIQ_LIB::modules::measures::UnifiedQualityScore, [197](#)
- ExecuteAll
 - OFIQ_LIB::modules::measures::Executor, [78](#)
- ExecuteScalarConversion
 - OFIQ_LIB::modules::measures::Measure, [133](#), [134](#)
- Executor
 - OFIQ_LIB::modules::measures::Executor, [78](#)
- Executor.h, [230](#), [231](#)
- ExpandKey
 - OFIQ_LIB::modules::measures::Measure, [134](#)
- ExposureRange
 - OFIQ_LIB, [37](#)
- ExpressionNeutrality
 - OFIQ, [34](#)
 - OFIQ_LIB::modules::measures::ExpressionNeutrality, [80](#)
- ExpressionNeutrality.h, [231](#), [232](#)
- extendedMessage
 - OFIQ_LIB::OFIQError, [152](#)
- extractLandmarks
 - OFIQ_LIB::FaceLandmarkExtractorInterface, [90](#)
- eye_g
 - OFIQ_LIB::modules::segmentations, [56](#)
- EyesOpen
 - OFIQ, [34](#)
 - OFIQ_LIB::modules::measures::EyesOpen, [83](#)
- EyesOpen.h, [233](#), [234](#)
- EyesVisible
 - OFIQ, [34](#)
 - OFIQ_LIB::modules::measures::EyesVisible, [85](#)
- EyesVisible.h, [234](#), [235](#)
- face
 - OFIQ_LIB::modules::segmentations, [56](#)
- FACE_CONTOUR
 - OFIQ_LIB::modules::landmarks, [48](#)
- FaceDetectionError
 - OFIQ, [35](#)
- faceDetector
 - OFIQ::BoundingBox, [64](#)
 - OFIQ_LIB::NeuronalNetworkContainer, [147](#)
- FaceDetectorType
 - OFIQ, [33](#)
- FaceImageQualityAssessment
 - OFIQ::FaceImageQualityAssessment, [88](#)
- FaceLandmarkExtractionError
 - OFIQ, [35](#)
- FaceLandmarks
 - OFIQ::FaceLandmarks, [91](#)
- FaceMap
 - OFIQ_LIB::modules::landmarks, [47](#)
 - OFIQ_LIB::modules::landmarks::adnet, [50](#)
- FaceMeasures
 - OFIQ_LIB::modules::landmarks::FaceMeasures, [92](#)
- FaceMeasures.h, [216](#), [218](#)
- faceOcclusionExtractor
 - OFIQ_LIB::NeuronalNetworkContainer, [147](#)
- FaceOcclusionPrevention
 - OFIQ, [34](#)
 - OFIQ_LIB::modules::measures::FaceOcclusionPrevention, [97](#)
- FaceOcclusionPrevention.h, [235](#), [236](#)
- FaceOcclusionSegmentation
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, [99](#)
- FaceOcclusionSegmentation.h, [263](#), [264](#)
- FaceOcclusionSegmentationError
 - OFIQ, [35](#)
- faceOcclusionSegmentationImage
 - OFIQ_LIB::Session, [181](#)
- FacePairMap
 - OFIQ_LIB::modules::landmarks, [47](#)
 - OFIQ_LIB::modules::landmarks::adnet, [50](#)
- FaceParsing
 - OFIQ_LIB::modules::segmentations::FaceParsing, [104](#)
- FaceParsing.h, [264](#), [265](#)
- FaceParsingError
 - OFIQ, [35](#)
- faceParsingImage
 - OFIQ_LIB::Session, [181](#)
- FaceParts
 - OFIQ_LIB::modules::landmarks, [48](#)
- FaceParts.h, [218](#), [220](#)
- faceRegionAlpha
 - OFIQ_LIB::modules::measures::Sharpness, [185](#)
- FailureToAssess
 - OFIQ, [34](#)

- findLargestBoundingBox
 - OFIQ_LIB, 41
- FOREHEAD
 - OFIQ_LIB::modules::landmarks, 48
- forehead
 - OFIQ_LIB::modules::landmarks::adnet, 50
- GenerateId
 - OFIQ_LIB::Session, 175
- getAlignedFace
 - OFIQ_LIB::Session, 175
- getAlignedFaceLandmarkedRegion
 - OFIQ_LIB::Session, 175
- getAlignedFaceLandmarks
 - OFIQ_LIB::Session, 175
- getAlignedFaceTransformationMatrix
 - OFIQ_LIB::Session, 176
- GetBool
 - OFIQ_LIB::Configuration, 69, 70
- GetClassifierFocusFeatures
 - OFIQ_LIB::modules::measures::Sharpness, 184
- GetCroppedImages
 - OFIQ_LIB::modules::measures::Sharpness, 184
- getDataDir
 - OFIQ_LIB::Configuration, 70
- getDetectedFaces
 - OFIQ_LIB::Session, 176
- GetDistance
 - OFIQ_LIB::modules::landmarks::FaceMeasures, 92, 93
- GetFaceMask
 - OFIQ_LIB::modules::landmarks::FaceMeasures, 93
- GetFaceOcclusionSegmentation
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 237, 238
 - 100
- getFaceOcclusionSegmentationImage
 - OFIQ_LIB::Session, 176
- getFaceParsingImage
 - OFIQ_LIB::Session, 176
- getFacePart
 - OFIQ_LIB::modules::landmarks::PartExtractor, 162
- getImplementation
 - OFIQ::Interface, 123
- getLandmarks
 - OFIQ_LIB::Session, 176
- GetLastSessionId
 - OFIQ_LIB::SegmentationExtractorInterface, 171
- GetLuminanceImageFromBGR
 - OFIQ_LIB, 42
- GetMask
 - OFIQ_LIB::SegmentationExtractorInterface, 171
- GetMaxPairDistance
 - OFIQ_LIB::modules::landmarks::FaceMeasures, 93
- GetMeasureName
 - OFIQ_LIB::modules::measures::Measure, 134
- GetMeasures
 - OFIQ_LIB::modules::measures::Executor, 78
- GetMiddle
 - OFIQ_LIB::modules::landmarks::FaceMeasures, 94, 95
- GetName
 - OFIQ_LIB::modules::measures::Measure, 135
- GetNormalizedHistogram
 - OFIQ_LIB, 42
- GetNumber
 - OFIQ_LIB::Configuration, 70, 71
- getNumberOfOutputNodes
 - ONNXRuntimeSegmentation, 158
- getPairsForPart
 - OFIQ_LIB::modules::landmarks::PartExtractor, 163
- getPose
 - OFIQ_LIB::Session, 177
- GetQualityMeasure
 - OFIQ_LIB::modules::measures::Measure, 135
- GetString
 - OFIQ_LIB::Configuration, 71
- GetStringList
 - OFIQ_LIB::Configuration, 72
- h
 - OFIQ_LIB::modules::measures::SigmoidParameters, 187
- hair
 - OFIQ_LIB::modules::segmentations, 56
- hat
 - OFIQ_LIB::modules::segmentations, 56
- HeadPose
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::HeadPose, 109
- HeadPose3DDFAV2
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 111
- HeadPose3DDFAV2.h, 260, 261
- HeadPosePitch
 - OFIQ, 34
- HeadPoseRoll
 - OFIQ, 34
- HeadPoseYaw
 - OFIQ, 34
- HeadSize
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::HeadSize, 115
- HeadSize.h, 238, 239
- height
 - OFIQ::BoundingBox, 64
 - OFIQ::Image, 119
- Id
 - OFIQ_LIB::Session, 177
- id
 - OFIQ_LIB::Session, 181
- IlluminationUniformity
 - OFIQ, 33

- OFIQ_LIB::modules::measures::IlluminationUniformity, 117
- IlluminationUniformity.h, 239, 240
- Image
 - OFIQ::Image, 119
- image
 - OFIQ_LIB::Session, 177
- image_io.h, 271, 272
- image_utils.h, 272, 273
- ImageReadingError
 - OFIQ, 35
- imageSize
 - OFIQ_LIB::modules::segmentations::FaceParsing, 107
- ImageWritingError
 - OFIQ, 35
- info
 - OFIQ::ReturnStatus, 169
- init_session
 - ONNXRuntimeSegmentation, 158
- initialize
 - OFIQ::Interface, 123
 - OFIQ_LIB::OFIQImpl, 155
 - ONNXRuntimeSegmentation, 159
- inputShape
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2OFIQ_LIB::modules::measures, 112
- InterEyeDistance
 - OFIQ, 34
 - OFIQ_LIB::modules::landmarks::FaceMeasures, 95
 - OFIQ_LIB::modules::measures::InterEyeDistance, 121
- InterEyeDistance.h, 241, 242
- I_brow
 - OFIQ_LIB::modules::segmentations, 55
- I_ear
 - OFIQ_LIB::modules::segmentations, 56
- I_eye
 - OFIQ_LIB::modules::segmentations, 55
- I_lip
 - OFIQ_LIB::modules::segmentations, 56
- landmarkExtractor
 - OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor, 59
 - OFIQ_LIB::NeuronalNetworkContainer, 147
- LandmarkId
 - OFIQ_LIB::modules::landmarks, 47
- LandmarkIdPair
 - OFIQ_LIB::modules::landmarks, 48
- LandmarkIdPairs
 - OFIQ_LIB::modules::landmarks, 48
- LandmarkIds
 - OFIQ_LIB::modules::landmarks, 48
- LandmarkPair
 - OFIQ_LIB::modules::landmarks::LandmarkPair, 125
- LandmarkPoint
 - OFIQ::LandmarkPoint, 127
- Landmarks
 - OFIQ, 32
- landmarks
 - OFIQ::FaceLandmarks, 91
 - OFIQ_LIB::Session, 181
- landmarks.h, 220, 221
- LandmarkType
 - OFIQ, 33
- lastSessionId
 - OFIQ_LIB::PoseEstimatorInterface, 166
 - OFIQ_LIB::SegmentationExtractorInterface, 172
- LEFT_EYE
 - OFIQ_LIB::modules::landmarks, 48
- LEFT_EYE_CORNERS
 - OFIQ_LIB::modules::landmarks, 48
- leftEye
 - OFIQ_LIB::modules::landmarks::adnet, 50
- leftEyeCorners
 - OFIQ_LIB::modules::landmarks::adnet, 50
- LeftwardCropOfTheFacelImage
 - OFIQ, 34
- LM_98
 - OFIQ, 33
- log
 - Lower
 - OFIQ_LIB::modules::landmarks::LandmarkPair, 126
- Luminance
 - OFIQ, 33
 - OFIQ_LIB::modules::measures::Luminance, 129
- Luminance.h, 242, 243
- LuminanceMean
 - OFIQ, 33
- LuminanceVariance
 - OFIQ, 33
- m_crop
 - OFIQ_LIB::modules::measures::CompressionArtifacts, 67
- m_crop_bottom
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 61
- m_crop_left
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 61
- m_crop_right
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 62
- m_crop_top
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 62
- m_dataDir
 - OFIQ_LIB::Configuration, 73
- m_dim
 - OFIQ_LIB::modules::measures::CompressionArtifacts, 67
- m_emptySession

- OFIQ_LIB::OFIQImpl, 157
- m_erosion_kernel_size
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 62
- m_executorPtr
 - OFIQ_LIB::OFIQImpl, 157
- m_expected_image_height
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 112
- m_expected_image_number_of_channels
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
- m_expected_image_width
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
- m_inputShape
 - ONNXRuntimeSegmentation, 159
- m_measure
 - OFIQ_LIB::modules::measures::Measure, 136
- m_memory_info
 - ONNXRuntimeSegmentation, 159
- m_number_of_input_elements
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
- m_onnxRuntimeEnv
 - OFIQ_LIB::modules::measures::CompressionArtifacts, 68
 - OFIQ_LIB::modules::measures::UnifiedQualityScore, 197
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 107
- m_onnxRuntimeEnvCNN1
 - OFIQ_LIB::modules::measures::ExpressionNeutrality, 81
- m_onnxRuntimeEnvCNN2
 - OFIQ_LIB::modules::measures::ExpressionNeutrality, 81
- m_ort_session
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
 - ONNXRuntimeSegmentation, 160
- m_ortenv
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
 - ONNXRuntimeSegmentation, 160
- m_target_height
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 62
- m_target_width
 - OFIQ_LIB::modules::measures::BackgroundUniformity, 62
- mainpage.h, 199
- MakeGreyImage
 - OFIQ_LIB, 42
- makeSquareBoundingBox
 - OFIQ_LIB, 43
- makeSquareBoundingBoxWithPadding
 - OFIQ_LIB, 43
- masks
 - OFIQ_LIB::SegmentationExtractorInterface, 172
- Measure
 - OFIQ_LIB::modules::measures::Measure, 132
 - Measure.h, 243, 244
 - MeasureFactory
 - OFIQ_LIB::modules::measures::MeasureFactory, 137
 - MeasureFactory.h, 246, 247
 - measures
 - OFIQ_LIB::modules::measures::Executor, 78
- OFIQ_LIB::OFIQError, 152
- minimalRelativeFaceSize
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 192
- MissingConfigParamError
 - OFIQ, 35
- modelConfigItem
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 101
 - OFIQ_LIB::modules::segmentations::FaceParsing, 107
- modelFile
 - OFIQ_LIB::modules::measures::Sharpness, 185
- mouth
 - OFIQ_LIB::modules::segmentations, 56
- MOUTH_CENTER
 - OFIQ_LIB::modules::landmarks, 48
- MOUTH_INNER
 - OFIQ_LIB::modules::landmarks, 48
- MOUTH_OUTER
 - OFIQ_LIB::modules::landmarks, 48
- MouthClosed
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::MouthClosed, 139
 - MouthClosed.h, 247, 248
- mouthInner
 - OFIQ_LIB::modules::landmarks::adnet, 51
- MouthOcclusionPrevention
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::MouthOcclusionPrevention, 141
 - MouthOcclusionPrevention.h, 248, 249
- mouthOuter
 - OFIQ_LIB::modules::landmarks::adnet, 51
- NaturalColour
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::NaturalColour, 144
 - NaturalColour.h, 250, 251
- neck
 - OFIQ_LIB::modules::segmentations, 56
- neck_l
 - OFIQ_LIB::modules::segmentations, 56
- networks

- OFIQ_LIB::OFIQImpl, 157
- NeuronalNetworkContainer
 - OFIQ_LIB::NeuronalNetworkContainer, 146
- NeuronalNetworkContainer.h, 274
- NoHeadCoverings
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::NoHeadCoverings, 149
- NoHeadCoverings.h, 251, 252
- nose
 - OFIQ_LIB::modules::segmentations, 56
- NOSETIP
 - OFIQ_LIB::modules::landmarks, 48
- nosetip
 - OFIQ_LIB::modules::landmarks::adnet, 51
- NotImplemented
 - OFIQ, 35
- NotInitialized
 - OFIQ, 34
- NotSet
 - OFIQ, 33, 34
- numTrees
 - OFIQ_LIB::modules::measures::Sharpness, 185
- OFIQ, 31
 - BackgroundUniformity, 33
 - CompressionArtifacts, 34
 - CropOfTheFacelImage, 34
 - DownwardCropOfTheFacelImage, 34
 - DynamicRange, 34
 - ExpressionNeutrality, 34
 - EyesOpen, 34
 - EyesVisible, 34
 - FaceDetectionError, 35
 - FaceDetectorType, 33
 - FaceLandmarkExtractionError, 35
 - FaceOcclusionPrevention, 34
 - FaceOcclusionSegmentationError, 35
 - FaceParsingError, 35
 - FailureToAssess, 34
 - HeadPose, 34
 - HeadPosePitch, 34
 - HeadPoseRoll, 34
 - HeadPoseYaw, 34
 - HeadSize, 34
 - IlluminationUniformity, 33
 - ImageReadingError, 35
 - ImageWritingError, 35
 - InterEyeDistance, 34
 - Landmarks, 32
 - LandmarkType, 33
 - LeftwardCropOfTheFacelImage, 34
 - LM_98, 33
 - Luminance, 33
 - LuminanceMean, 33
 - LuminanceVariance, 33
 - MissingConfigParamError, 35
 - MouthClosed, 34
 - MouthOcclusionPrevention, 34
 - NaturalColour, 34
 - NoHeadCoverings, 34
 - NotImplemented, 35
 - NotInitialized, 34
 - NotSet, 33, 34
 - OPENCVSSD, 33
 - operator<<, 35
 - OverExposurePrevention, 33
 - QualityAssessmentError, 35
 - QualityAssessments, 32
 - QualityMeasure, 33
 - QualityMeasureReturnCode, 34
 - ReturnCode, 34
 - RightwardCropOfTheFacelImage, 34
 - Sharpness, 34
 - SingleFacePresent, 34
 - Success, 34, 35
 - UnderExposurePrevention, 33
 - UnifiedQualityScore, 33
 - UnknownConfigParamError, 35
 - UnknownError, 35
 - UpwardCropOfTheFacelImage, 34
- OFIQ::BoundingBox, 63
 - BoundingBox, 63
 - faceDetector, 64
 - height, 64
 - width, 64
 - xleft, 64
 - ytop, 64
- OFIQ::FacelImageQualityAssessment, 88
 - boundingBox, 89
 - FacelImageQualityAssessment, 88
 - qAssessments, 89
- OFIQ::FaceLandmarks, 91
 - FaceLandmarks, 91
 - landmarks, 91
 - type, 91
- OFIQ::Image, 118
 - data, 119
 - depth, 119
 - height, 119
 - Image, 119
 - size, 119
 - width, 120
- OFIQ::Interface, 122
 - ~Interface, 123
 - getImplementation, 123
 - initialize, 123
 - scalarQuality, 124
 - vectorQuality, 124
- OFIQ::LandmarkPoint, 126
 - LandmarkPoint, 127
 - x, 127
 - y, 127
- OFIQ::QualityMeasureResult, 167
 - code, 168
 - QualityMeasureResult, 167
 - rawScore, 168

- scalar, 168
 - OFIQ:: - code, 169
 - info, 169
 - ReturnStatus, 169
- OFIQ_EXPORT
 - ofiq_lib.h, 201
- OFIQ_LIB, 35
 - alignImage, 37
 - CalculateExposure, 38
 - calculateEyeCenter, 38
 - CalculateReferencePoints, 38
 - CalculateRegionOfInterest, 39
 - ColorConvert, 39
 - ComputeBrightnessAspect, 40
 - ConvertBGRToCIELAB, 40
 - copyToCvImage, 40
 - Cubic, 41
 - EulerAngle, 37
 - ExposureRange, 37
 - findLargestBoundingBox, 41
 - GetLuminanceImageFromBGR, 42
 - GetNormalizedHistogram, 42
 - MakeGreylImage, 42
 - makeSquareBoundingBox, 43
 - makeSquareBoundingBoxWithPadding, 43
 - readImage, 43
 - rotationMatrixToEulerAngles, 45
 - tmetric, 45
- ofiq_lib.h, 200, 201
 - OFIQ_EXPORT, 201
- OFIQ_LIB::Configuration, 68
 - Configuration, 69
 - GetBool, 69, 70
 - getDataDir, 70
 - GetNumber, 70, 71
 - GetString, 71
 - GetStringList, 72
 - m_dataDir, 73
 - parameters, 73
 - SetDataDir, 72
- OFIQ_LIB::FaceDetectorInterface, 86
 - ~FaceDetectorInterface, 87
 - detectFaces, 87
 - UpdateFaces, 87
- OFIQ_LIB::FaceLandmarkExtractorInterface, 89
 - ~FaceLandmarkExtractorInterface, 90
 - extractLandmarks, 90
 - updateLandmarks, 90
- OFIQ_LIB::modules, 45
- OFIQ_LIB::modules::detectors, 46
- OFIQ_LIB::modules::detectors::SSDFaceDetector, 190
 - ~SSDFaceDetector, 192
 - confidenceThreshold, 192
 - dnnNet, 192
 - minimalRelativeFaceSize, 192
 - padding, 193
 - SSDFaceDetector, 191
 - UpdateFaces, 192
- OFIQ_LIB::modules::landmarks, 46
 - CHIN, 48
 - FACE_CONTOUR, 48
 - FaceMap, 47
 - FacePairMap, 47
 - FaceParts, 48
 - FOREHEAD, 48
 - LandmarkId, 47
 - LandmarkIdPair, 48
 - LandmarkIdPairs, 48
 - LandmarkIds, 48
 - LEFT_EYE, 48
 - LEFT_EYE_CORNERS, 48
 - MOUTH_CENTER, 48
 - MOUTH_INNER, 48
 - MOUTH_OUTER, 48
 - NOSETIP, 48
 - RIGHT_EYE, 48
 - RIGHT_EYE_CORNERS, 48
- OFIQ_LIB::modules::landmarks::adnet, 49
 - chin, 49
 - contour, 49
 - FaceMap, 50
 - FacePairMap, 50
 - forehead, 50
 - leftEye, 50
 - leftEyeCorners, 50
 - mouthInner, 51
 - mouthOuter, 51
 - nosetip, 51
 - pairsInnerLip, 51
 - pairsLeftEye, 51
 - pairsMouthCenter, 51
 - pairsRightEye, 52
 - rightEye, 52
 - rightEyeCorners, 52
- OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor, 57
 - ~ADNetFaceLandmarkExtractor, 58
 - ADNetFaceLandmarkExtractor, 58
 - landmarkExtractor, 59
 - updateLandmarks, 58
- OFIQ_LIB::modules::landmarks::FaceMeasures, 92
 - FaceMeasures, 92
 - GetDistance, 92, 93
 - GetFaceMask, 93
 - GetMaxPairDistance, 93
 - GetMiddle, 94, 95
 - InterEyeDistance, 95
- OFIQ_LIB::modules::landmarks::LandmarkPair, 125
 - LandmarkPair, 125
 - Lower, 126
 - Upper, 126
- OFIQ_LIB::modules::landmarks::PartExtractor, 162
 - getFacePart, 162
 - getPairsForPart, 163
- OFIQ_LIB::modules::measures, 52

- execLogActive, 54
- log, 54
- OFIQ_LIB::modules::measures::BackgroundUniformity, 59
 - BackgroundUniformity, 61
 - Execute, 61
 - m_crop_bottom, 61
 - m_crop_left, 61
 - m_crop_right, 62
 - m_crop_top, 62
 - m_erosion_kernel_size, 62
 - m_target_height, 62
 - m_target_width, 62
- OFIQ_LIB::modules::measures::CompressionArtifacts, 65
 - CompressionArtifacts, 66
 - Execute, 67
 - m_crop, 67
 - m_dim, 67
 - m_onnxRuntimeEnv, 68
- OFIQ_LIB::modules::measures::CropOfTheFacelImage, 73
 - CropOfTheFacelImage, 74
 - Execute, 75
- OFIQ_LIB::modules::measures::DynamicRange, 75
 - DynamicRange, 76
 - Execute, 77
- OFIQ_LIB::modules::measures::Executor, 77
 - ExecuteAll, 78
 - Executor, 78
 - GetMeasures, 78
 - measures, 78
- OFIQ_LIB::modules::measures::ExpressionNeutrality, 79
 - classifier, 81
 - Execute, 81
 - ExpressionNeutrality, 80
 - m_onnxRuntimeEnvCNN1, 81
 - m_onnxRuntimeEnvCNN2, 81
- OFIQ_LIB::modules::measures::EyesOpen, 82
 - Execute, 83
 - EyesOpen, 83
- OFIQ_LIB::modules::measures::EyesVisible, 84
 - Execute, 86
 - EyesVisible, 85
- OFIQ_LIB::modules::measures::FaceOcclusionPrevention, 96
 - Execute, 97
 - FaceOcclusionPrevention, 97
- OFIQ_LIB::modules::measures::HeadPose, 108
 - Execute, 109
 - HeadPose, 109
- OFIQ_LIB::modules::measures::HeadSize, 114
 - Execute, 115
 - HeadSize, 115
- OFIQ_LIB::modules::measures::IlluminationUniformity, 116
 - Execute, 118
 - IlluminationUniformity, 117
- OFIQ_LIB::modules::measures::InterEyeDistance, 120
 - Execute, 122
 - InterEyeDistance, 121
- OFIQ_LIB::modules::measures::Luminance, 128
 - Execute, 129
 - Luminance, 129
- OFIQ_LIB::modules::measures::Measure, 130
 - ~Measure, 132
 - AddSigmoid, 132
 - configuration, 136
 - Execute, 133
 - ExecuteScalarConversion, 133, 134
 - ExpandKey, 134
 - GetMeasureName, 134
 - GetName, 135
 - GetQualityMeasure, 135
 - m_measure, 136
 - Measure, 132
 - ScalarConversion, 135
 - SetQualityMeasure, 135
 - Sigmoid, 136
 - sigmoidMap, 137
- OFIQ_LIB::modules::measures::MeasureFactory, 137
 - CreateMeasure, 137
 - MeasureFactory, 137
- OFIQ_LIB::modules::measures::MouthClosed, 138
 - Execute, 140
 - MouthClosed, 139
- OFIQ_LIB::modules::measures::MouthOcclusionPrevention, 140
 - Execute, 142
 - MouthOcclusionPrevention, 141
- OFIQ_LIB::modules::measures::NaturalColour, 142
 - CalculateScore, 144
 - CreateMaskedImage, 145
 - Execute, 145
 - NaturalColour, 144
 - ReduceImageToRegionOfInterest, 145
- OFIQ_LIB::modules::measures::NoHeadCoverings, 148
 - Execute, 150
 - NoHeadCoverings, 149
 - threshold, 150
- OFIQ_LIB::modules::measures::OverExposurePrevention, 160
 - Execute, 162
 - OverExposurePrevention, 161
- OFIQ_LIB::modules::measures::Sharpness, 182
 - Execute, 184
 - faceRegionAlpha, 185
 - GetClassifierFocusFeatures, 184
 - GetCroppedImages, 184
 - modelFile, 185
 - numTrees, 185
 - rtree, 185
 - Sharpness, 183
 - useAligned, 185

- OFIQ_LIB::modules::measures::SigmoidParameters,
 - 186
 - a, 187
 - h, 187
 - Reset, 187
 - round, 187
 - s, 188
 - setInverse, 187
 - SigmoidParameters, 187
 - w, 188
 - x0, 188
- OFIQ_LIB::modules::measures::SingleFacePresent,
 - 188
 - Execute, 190
 - SingleFacePresent, 190
- OFIQ_LIB::modules::measures::UnderExposurePrevention,
 - 193
 - Execute, 195
 - UnderExposurePrevention, 194
- OFIQ_LIB::modules::measures::UnifiedQualityScore,
 - 195
 - Execute, 197
 - m_onnxRuntimeEnv, 197
 - UnifiedQualityScore, 196
- OFIQ_LIB::modules::poseEstimators, 54
- OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2,
 - 110
 - ~HeadPose3DDFAV2, 111
 - CropImage, 112
 - HeadPose3DDFAV2, 111
 - inputShape, 112
 - m_expected_image_height, 112
 - m_expected_image_number_of_channels, 113
 - m_expected_image_width, 113
 - m_number_of_input_elements, 113
 - m_ort_session, 113
 - m_ortenv, 113
 - paramPoseEstimatorModel, 113
 - updatePose, 112
- OFIQ_LIB::modules::segmentations, 55
 - background, 55
 - cloth, 56
 - ear_r, 56
 - eye_g, 56
 - face, 56
 - hair, 56
 - hat, 56
 - l_brow, 55
 - l_ear, 56
 - l_eye, 55
 - l_lip, 56
 - mouth, 56
 - neck, 56
 - neck_l, 56
 - nose, 56
 - r_brow, 55
 - r_ear, 56
 - r_eye, 55
 - SegmentClassLabels, 55
 - skin, 55
 - u_lip, 56
- OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation,
 - 98
 - ~FaceOcclusionSegmentation, 100
 - cropBottom, 101
 - cropLeft, 101
 - cropRight, 101
 - cropTop, 101
 - FaceOcclusionSegmentation, 99
 - GetFaceOcclusionSegmentation, 100
 - m_onnxRuntimeEnv, 101
 - modelConfigItem, 101
 - scaledHeight, 102
 - scaledWidth, 102
 - segmentationImage, 102
 - UpdateMask, 100
- OFIQ_LIB::modules::segmentations::FaceParsing, 102
 - ~FaceParsing, 104
 - CalculateClassIds, 105
 - CreateBlob, 105
 - cropBottom, 106
 - cropLeft, 106
 - cropRight, 106
 - cropTop, 107
 - FaceParsing, 104
 - imageSize, 107
 - m_onnxRuntimeEnv, 107
 - modelConfigItem, 107
 - segmentationImage, 107
 - setImage, 105
 - UpdateMask, 106
- OFIQ_LIB::NeuronalNetworkContainer, 146
 - faceDetector, 147
 - faceOcclusionExtractor, 147
 - landmarkExtractor, 147
 - NeuronalNetworkContainer, 146
 - poseEstimator, 147
 - segmentationExtractor, 147
- OFIQ_LIB::OFIQError, 150
 - extendedMessage, 152
 - message, 152
 - OFIQError, 151
 - returnCode, 152
 - what, 151
 - whatCode, 152
- OFIQ_LIB::OFIQImpl, 152
 - ~OFIQImpl, 154
 - alignFacelImage, 154
 - config, 156
 - CreateExecutor, 154
 - CreateNetworks, 155
 - dummyAssessment, 156
 - dummyImage, 156
 - initialize, 155
 - m_emptySession, 157
 - m_executorPtr, 157

- networks, 157
- OFIQImpl, 154
- performPreprocessing, 155
- scalarQuality, 155
- vectorQuality, 156
- OFIQ_LIB::Point2i, 164
 - x, 164
 - y, 164
- OFIQ_LIB::PoseEstimatorInterface, 165
 - ~PoseEstimatorInterface, 166
 - estimatePose, 166
 - EulerAngle, 165
 - lastSessionId, 166
 - pose, 166
 - updatePose, 166
- OFIQ_LIB::SegmentationExtractorInterface, 170
 - ~SegmentationExtractorInterface, 171
 - GetLastSessionId, 171
 - GetMask, 171
 - lastSessionId, 172
 - masks, 172
 - UpdateMask, 171
- OFIQ_LIB::Session, 172
 - _assessment, 180
 - _image, 180
 - alignedFace, 180
 - alignedFacelandmarkedRegion, 180
 - alignedFaceLandmarks, 180
 - alignedFaceTransformationMatrix, 180
 - assessment, 175
 - detectedFaces, 180
 - faceOcclusionSegmentationImage, 181
 - faceParsingImage, 181
 - GenerateId, 175
 - getAlignedFace, 175
 - getAlignedFaceLandmarkedRegion, 175
 - getAlignedFaceLandmarks, 175
 - getAlignedFaceTransformationMatrix, 176
 - getDetectedFaces, 176
 - getFaceOcclusionSegmentationImage, 176
 - getFaceParsingImage, 176
 - getLandmarks, 176
 - getPose, 177
 - Id, 177
 - id, 181
 - image, 177
 - landmarks, 181
 - pose, 181
 - Session, 174
 - setAlignedFace, 177
 - setAlignedFaceLandmarkedRegion, 178
 - setAlignedFaceLandmarks, 178
 - setAlignedFaceTransformationMatrix, 178
 - setDetectedFaces, 178
 - setFaceOcclusionSegmentationImage, 179
 - setFaceParsingImage, 179
 - setLandmarks, 179
 - setPose, 179
- ofiq_lib_impl.h, 201, 202
- ofiq_structs.h, 203, 205
- OFIQError
 - OFIQ_LIB::OFIQError, 151
- OFIQError.h, 275, 276
- OFIQImpl
 - OFIQ_LIB::OFIQImpl, 154
- ONNXRTSegmentation.h, 266, 267
- ONNXRuntimeSegmentation, 157
 - ~ONNXRuntimeSegmentation, 158
 - getNumberOfOutputNodes, 158
 - init_session, 158
 - initialize, 159
 - m_inputShape, 159
 - m_memory_info, 159
 - m_ort_session, 160
 - m_ortenv, 160
 - ONNXRuntimeSegmentation, 158
 - run, 159
- Open Source Face Image Quality (OFIQ) Library, 1
- opencv_ssd_face_detector.h, 210, 211
- OPENCVSSD
 - OFIQ, 33
- operator<<
 - OFIQ, 35
- OverExposurePrevention
 - OFIQ, 33
 - OFIQ_LIB::modules::measures::OverExposurePrevention, 161
- OverExposurePrevention.h, 252, 253
- padding
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 193
- pairsInnerLip
 - OFIQ_LIB::modules::landmarks::adnet, 51
- pairsLeftEye
 - OFIQ_LIB::modules::landmarks::adnet, 51
- pairsMouthCenter
 - OFIQ_LIB::modules::landmarks::adnet, 51
- pairsRightEye
 - OFIQ_LIB::modules::landmarks::adnet, 52
- parameters
 - OFIQ_LIB::Configuration, 73
- paramPoseEstimatorModel
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 113
- PartExtractor.h, 221, 223
- performPreprocessing
 - OFIQ_LIB::OFIQImpl, 155
- Point2f, 163
 - x, 164
 - y, 164
- pose
 - OFIQ_LIB::PoseEstimatorInterface, 166
 - OFIQ_LIB::Session, 181
- poseEstimator
 - OFIQ_LIB::NeuronalNetworkContainer, 147
- poseEstimators.h, 261, 262

- qAssessments
 - OFIQ::FaceImageQualityAssessment, 89
- QualityAssessmentError
 - OFIQ, 35
- QualityAssessments
 - OFIQ, 32
- QualityMeasure
 - OFIQ, 33
- QualityMeasureResult
 - OFIQ::QualityMeasureResult, 167
- QualityMeasureReturnCode
 - OFIQ, 34

- r_brow
 - OFIQ_LIB::modules::segmentations, 55
- r_ear
 - OFIQ_LIB::modules::segmentations, 56
- r_eye
 - OFIQ_LIB::modules::segmentations, 55
- rawScore
 - OFIQ::QualityMeasureResult, 168
- readImage
 - OFIQ_LIB, 43
- ReduceImageToRegionOfInterest
 - OFIQ_LIB::modules::measures::NaturalColour, 145
- Reset
 - OFIQ_LIB::modules::measures::SigmoidParameters, 187
- ReturnCode
 - OFIQ, 34
- returnCode
 - OFIQ_LIB::OFIQError, 152
- ReturnStatus
 - OFIQ::ReturnStatus, 169
- RIGHT_EYE
 - OFIQ_LIB::modules::landmarks, 48
- RIGHT_EYE_CORNERS
 - OFIQ_LIB::modules::landmarks, 48
- rightEye
 - OFIQ_LIB::modules::landmarks::adnet, 52
- rightEyeCorners
 - OFIQ_LIB::modules::landmarks::adnet, 52
- RightwardCropOfTheFaceImage
 - OFIQ, 34
- rotationMatrixToEulerAngles
 - OFIQ_LIB, 45
- round
 - OFIQ_LIB::modules::measures::SigmoidParameters, 187
- rtree
 - OFIQ_LIB::modules::measures::Sharpness, 185
- run
 - ONNXRuntimeSegmentation, 159

- s
 - OFIQ_LIB::modules::measures::SigmoidParameters, 188
- scalar
 - OFIQ::QualityMeasureResult, 168
- ScalarConversion
 - OFIQ_LIB::modules::measures::Measure, 135
- scalarQuality
 - OFIQ::Interface, 124
 - OFIQ_LIB::OFIQImpl, 155
- scaledHeight
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 102
- scaledWidth
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 102
- segmentationExtractor
 - OFIQ_LIB::NeuronalNetworkContainer, 147
- segmentationImage
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 102
 - OFIQ_LIB::modules::segmentations::FaceParsing, 107
- segmentations.h, 267, 269
- SegmentClassLabels
 - OFIQ_LIB::modules::segmentations, 55
- Session
 - OFIQ_LIB::Session, 174
- Session.h, 276, 277
- setAlignedFace
 - OFIQ_LIB::Session, 177
- setAlignedFaceLandmarkedRegion
 - OFIQ_LIB::Session, 178
- setAlignedFaceLandmarks
 - OFIQ_LIB::Session, 178
- setAlignedFaceTransformationMatrix
 - OFIQ_LIB::Session, 178
- SetDataDir
 - OFIQ_LIB::Configuration, 72
- setDetectedFaces
 - OFIQ_LIB::Session, 178
- setFaceOcclusionSegmentationImage
 - OFIQ_LIB::Session, 179
- setFaceParsingImage
 - OFIQ_LIB::Session, 179
- SetImage
 - OFIQ_LIB::modules::segmentations::FaceParsing, 105
- setInverse
 - OFIQ_LIB::modules::measures::SigmoidParameters, 187
- setLandmarks
 - OFIQ_LIB::Session, 179
- setPose
 - OFIQ_LIB::Session, 179
- SetQualityMeasure
 - OFIQ_LIB::modules::measures::Measure, 135
- Sharpness
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::Sharpness, 183
- Sharpness.h, 254, 255
- Sigmoid

- OFIQ_LIB::modules::measures::Measure, 136
- sigmoidMap
 - OFIQ_LIB::modules::measures::Measure, 137
- SigmoidParameters
 - OFIQ_LIB::modules::measures::SigmoidParameters, Upper 187
- SingleFacePresent
 - OFIQ, 34
 - OFIQ_LIB::modules::measures::SingleFacePresent, 190
- SingleFacePresent.h, 255, 256
- size
 - OFIQ::Image, 119
- skin
 - OFIQ_LIB::modules::segmentations, 55
- SSDFaceDetector
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 191
- Success
 - OFIQ, 34, 35
- threshold
 - OFIQ_LIB::modules::measures::NoHeadCoverings, 150
- tmetric
 - OFIQ_LIB, 45
- type
 - OFIQ::FaceLandmarks, 91
- u_lip
 - OFIQ_LIB::modules::segmentations, 56
- UnderExposurePrevention
 - OFIQ, 33
 - OFIQ_LIB::modules::measures::UnderExposurePrevention, 194
- UnderExposurePrevention.h, 256, 257
- UnifiedQualityScore
 - OFIQ, 33
 - OFIQ_LIB::modules::measures::UnifiedQualityScore, *y* 196
- UnifiedQualityScore.h, 258, 259
- UnknownConfigParamError
 - OFIQ, 35
- UnknownError
 - OFIQ, 35
- UpdateFaces
 - OFIQ_LIB::FaceDetectorInterface, 87
 - OFIQ_LIB::modules::detectors::SSDFaceDetector, 192
- updateLandmarks
 - OFIQ_LIB::FaceLandmarkExtractorInterface, 90
 - OFIQ_LIB::modules::landmarks::ADNetFaceLandmarkExtractor, 58
- UpdateMask
 - OFIQ_LIB::modules::segmentations::FaceOcclusionSegmentation, 100
 - OFIQ_LIB::modules::segmentations::FaceParsing, 106
 - OFIQ_LIB::SegmentationExtractorInterface, 171
- updatePose
 - OFIQ_LIB::modules::poseEstimators::HeadPose3DDFAV2, 112
 - OFIQ_LIB::PoseEstimatorInterface, 166
 - OFIQ_LIB::modules::landmarks::LandmarkPair, 126
- UpwardCropOfTheFacelImage
 - OFIQ, 34
- useAligned
 - OFIQ_LIB::modules::measures::Sharpness, 185
- utils.h, 278, 280
- vectorQuality
 - OFIQ::Interface, 124
 - OFIQ_LIB::OFIQImpl, 156
- w
 - OFIQ_LIB::modules::measures::SigmoidParameters, 188
- what
 - OFIQ_LIB::OFIQError, 151
- whatCode
 - OFIQ_LIB::OFIQError, 152
- width
 - OFIQ::BoundingBox, 64
 - OFIQ::Image, 120
- x
 - OFIQ::LandmarkPoint, 127
 - OFIQ_LIB::Point2i, 164
 - Point2f, 164
- x0
 - OFIQ_LIB::modules::measures::SigmoidParameters, 188
- xleft
 - OFIQ::BoundingBox, 64
 - OFIQ::LandmarkPoint, 127
 - OFIQ_LIB::Point2i, 164
 - Point2f, 164
- ytop
 - OFIQ::BoundingBox, 64